



Receiver for Java 10

Contents

Receiver for Java 10	5
Readme for Citrix Receiver for Java 10.0	7
Receiver for Java Feature Overview	10
Seamless Support	12
Connection Center	13
Receiver for Java Requirements	14
Deploying the Receiver for Java	15
To unpack the Receiver for Java package	16
Deploying Receiver for Java Through Web Interface	18
To configure fallback to Receiver for Java	19
Customizing the Receiver for Java Deployment	20
Using Private Root Certificates with Receiver for Java	22
Getting Started with the Sample HTML Files	23
Customizing the desktop.html File	25
To customize and use desktop.html	27
Customizing the seamless1.html File	29
To customize and use seamless1.html	30
Using Signed Java Applets	32
Example: To make a desktop for a server available to users	33
Configuring the Receiver for Java	34
To set the receiver language	35
To change the network protocol for the Receiver for Java	36
Configuring Server Browsing	37
To specify a business recovery server group	38
To change the client name	39
Passing Parameters to Applications	40
To pass a parameter to an application	41
To set the size and number of colors used for the session window	42
Showing and Hiding the Status Bar and Settings Button	43

To enable Session Reliability	44
Controlling Auto-Reconnect and Session Termination	45
Specifying Keyboard and Mouse Preferences	47
Supported Keyboard Layouts	50
Specifying Japanese IME Preferences	53
Specifying Hotkey Functions	54
To change the hotkey sequence from the default	56
User Device Mapping	57
Mapping Receiver Printers	59
ICAPrinterDrivers.txt File	60
To configure printers manually	61
Examples of Configuring Printers Manually	63
To enable receiver audio mapping	65
Connecting Through a Proxy Server	66
To enable proxy auto detection	67
Integrating the Receiver with the Secure Gateway or SSL Relay	69
To enable SSL and TLS	70
Configuring the Receiver for Use with Your Security Solution	71
Importing Root Certificates	73
Certificate Revocation List Checking	75
Certificate Chains	76
Connecting to a Server Across a Firewall	77
To specify ICA encryption	78
Configuring Kerberos Authentication	79
To configure the receiver for Kerberos logon	80
Locating Receiver Configuration and Device Files	81
Improving Performance of the Receiver for Java	83
Improving Performance over a Low-Bandwidth Connection	85
Limitations of the Receiver for Java	87
Working with Linux and Solaris	89
Working with the Mac OS X	90
Working with Windows Internet Explorer	91
Using the Receiver for Java on Japanese Operation Systems	92
Using Client-side IME Input Mode on Mac OS X	94
Parameters for the Receiver for Java	95
Security Integration Parameters	97
User Interface Parameters	99

Client Audio Mapping Parameters	101
Receiver Printer Mapping Parameters	102
Client Drive Mapping Parameters	103
Performance Tuning Parameters	104

Receiver for Java 10

Citrix Receiver for Java is a Java applet that provides access to applications running on a server farm from any computer device with Windows Internet Explorer 8 or Firefox 3.5. The applet is a download-and-run, zero-install client, optimized for use in Web environments where it is not possible or desirable to install software on the user device.

The receiver has the following advantages:

- You do not need to install any software on any user device. Users require only Internet Explorer 8 or Firefox 3.5, with Java SE Runtime Environment (JRE) 6 Update 18.
- At the most basic level of functionality, the applet is approximately 542KB in size, providing a faster download than any other receiver.

The applet resides on a Web server and is deployed using an HTML page with a customizable <applet> tag. Users run the receiver by opening the HTML page using one of the supported browsers with Java support. When the page opens, the Java applet is automatically downloaded to the user device. The applet then runs and connects to the server or published application specified in the <applet> tag.

Unlike the ActiveX Client or Win32 Web Client, which are downloaded once and then saved for future use by the user device, the applet is not stored permanently on the user's system. However, Java environments provide a separate cache for Java applets, which you configure in the plug-in control panel.

What's New

The following items are new with Receiver for Java 10:

- Supports for Citrix XenApp 6 on Windows Server 2008 R2
- Supports Windows Internet Explorer 8 or Firefox 3.5

In This Section

Readme for Citrix Receiver for Java 10.0	For known issues in this release, see <i>Readme for Citrix Receiver for Java 10.0</i> .
Receiver for Java Features and Requirements	Find an overview of the receiver as well as the requirements for this release.
Deploying the Receiver for Java	Obtain the receiver files and become familiar with their contents and how they work.
Configuring the Receiver for Java	Configure the receiver by customizing the receiver .html files.
Limitations of the Receiver for Java	Learn the limitations of the receiver within certain operating systems.
Parameters for the Receiver for Java	Use these parameters to provide additional features and customization.

Readme for Citrix Receiver for Java 10.0

Readme Version: 1.0

Contents

- Finding Documentation
- Getting Support
- Installation Issues
- Other Known Issues

Finding Documentation

To access complete and up-to-date product information, in Citrix eDocs, expand the topics for your product.

Licensing Documentation

To access licensing documentation, go to <http://support.citrix.com/proddocs/topic/technologies/lic-library-node-wrapper.html>.

Getting Support

Citrix provides technical support primarily through Citrix Solutions Advisors. Contact your supplier for first-line support or use Citrix Online Technical Support to find the nearest Citrix Solutions Advisor.

Citrix offers online technical support services on the [Citrix Support Web site](#). The Support page includes links to downloads, the Citrix Knowledge Center, Citrix Consulting Services, and other useful support pages.

Issues Resolved in this Release

Signing certificate expired August 6, 2010

The signing certificate included with the previously posted Citrix Receiver for Java 10 packages expired August 6, 2010. Updated packages with a three year certification are

available as of July 28, 2010. Download the latest packages to %Program Files%\Citrix\Web Interface\Version\Clients\Java (or for 64-bit computers, %Program FILES (x86)%\Citrix\Web Interface\Version\Clients\Java), moving the older Receiver files to another location. Expand the new packages into the empty folder.

Users cannot resize the window of published applications in multiple hop sessions

Users cannot resize the window of published applications in multiple hop sessions (a session within a session). [#218726]

All sessions and applications within a second session in a multiple hop scenario close

All sessions and applications within a second session in a multiple hop scenario are closed if any one session or application in that second session are closed by right-clicking the application in the task bar. [#218729]

ALT+TAB not working with multi-hop seamless applications

Users are not able to use ALT+TAB to switch between different application windows in the first and second sessions in cases of multiple hop sessions, when the Java client is used for the first session and a native client for the second session. [#220557]

Known Issues

Printers do not get mapped when connecting to server running XenApp 6

Printers do not get mapped when connecting to a server running XenApp 6. This happens because Windows Server 2008 R2 does not include PCL4 and PCL5c drivers. To resolve this, follow these steps:

1. Configure a Windows 2008 64-bit print server and publish two shared print queues using the following in-box drivers:
 - HP Color LaserJet 4500
 - HP LaserJet Series II
2. On a computer running Windows Server 2008 R2, log on as an administrator and connect to each of these print queues. The necessary drivers download and install from the print servers. [# 229812]

Audio files do not play with Windows Media Player when published on a Windows Server 2008 or Windows Server 2008 R2 computer

Audio files do not play with Windows Media Player as a published application or in a desktop session from a server running Windows Server 2008 or Windows Server 2008 R2. Other media players are not affected and may be used if available to the user as a published application or in a desktop session. [# 215564]

Session time zone does not synchronize with the user device time zone

The session time zone does not synchronize with the user device time zone. The time zone from the server is used, rather than the time zone from the user device. As a result, the time shown in the notification area reflects the server time zone. [#215566]

Session Sharing feature does not work properly with Windows Internet Explorer 8

When used with Windows Internet Explorer 8, Receiver for Java's Session Sharing feature does not work properly. Internet Explorer 8, by default, uses separate, self-contained processes for each tab and window. As a result, multiple receiver connection centers open, unable to detect each other, rather than multiple applications sharing a single connection center. To avoid this situation, in the registry of the user device, in HKEY_CURRENT_USER\Software\Microsoft\Internet Explorer\Main, add the new DWORD, TabProcGrowth, set to 0. [SR#60099632]

Caution: Editing the Registry incorrectly can cause serious problems that may require you to reinstall your operating system. Citrix cannot guarantee that problems resulting from the incorrect use of Registry Editor can be solved. Use Registry Editor at your own risk. Be sure to back up the registry before you edit it.

<http://www.citrix.com>

Receiver for Java Feature Overview

Ensuring the Availability of the Proper Java Environment

Citrix Receiver for Java requires Java SE Runtime Environment (JRE) 6 Update 18.

The Microsoft Java Virtual Machine (JVM) is no longer supported. Note that within a deployment comprising Web Interface, the Client for Java 8 is deployed for use with the Microsoft JVM.

SSL Support

Secure Sockets Layer (SSL) support, provided by the Java Secure Socket Extension (JSSE), is embedded in JRE 6 Update 18. Therefore, fewer packages are downloaded to the client device for SSL support. The `cryptojN.jar` library is no longer required and the `sslN.jar` library is reduced from 187KB to 28KB.

CRL Checking

Certificate Revocation List (CRL) checking is supported. When connecting to a server running XenApp using SSL or TLS, and CRL checking is enabled, the receiver checks whether or not the server's certificate is revoked. This feature improves the cryptographic authentication and overall security of the connection to the server running XenApp.

Kerberos Authentication

Kerberos authentication is supported when the client is running on Windows XP, Windows Vista, or Windows 7, with the necessary trust relationship between client and server Active Directory domains.

Kerberos logon requires Citrix XenApp 6 or XenApp 5 and works only between clients and servers that belong to the same or to trusted Windows Server 2003, Windows Server 2008, or Windows Server 2008 R2 domains. Servers must also be trusted for delegation, an option you configure through the Active Directory Users and Computers management tool.

Important: Kerberos support requires XML Service DNS address resolution to be enabled for the server farm, or reverse DNS resolution to be enabled for the Active Directory domain.

You can configure Kerberos-enabled UNIX and Microsoft Windows domains to allow users working on UNIX client devices to access XenApp using their UNIX Kerberos credentials.

Kerberos authentication is not supported when the client is running on Mac OS X client devices. For further information, see <http://developer.apple.com>.

NTLM Proxy Authentication

Windows NT LAN Manager (NTLM) proxy authentication is supported when the client is configured to access XenApp through a proxy server. The client must be running on Windows and connecting through a proxy server that supports NTLM (such as Microsoft Internet Security & Acceleration Server).

Session Reliability

Session reliability enables sessions to remain open and on screen when network connectivity is interrupted, therefore allowing client users to view the application while the network connection is restored. This feature is useful for mobile users with wireless connections.

Mac OS X Japanese Support

The client is now supported on Japanese Mac OS X.

ICA Browsing

ICA browsing is applicable when deploying the client without the Web Interface. Support for ICA browsing is no longer provided in the core archive; it is provided as a separate archive (JICA-browserN.jar).

Universal Print Driver Support

The Universal Print Driver (UPD) is a standard Windows print driver that encapsulates print jobs in Printer Control Language 4 (PCL4) format. A client-based interpreter renders the print job using the client device's local print driver and printing services. The UPD generates smaller print jobs, which can significantly improve performance when printing over WAN or dial-up connections. Using UPD also increases security on the server because the number of drivers used is restricted.

Receiver for Java supports only UPD1 (UPD2 and UPD3 support printing in color and at higher resolutions).

Seamless Support

Seamless support is provided as an option on Citrix Receiver for Java. It has three main aspects:

- Seamless windows
- Session sharing
- Connection Center, a tool that enables users to manipulate both seamless and non-seamless connections

To provide seamless support on Receiver for Java, Citrix recommends deploying the receiver through the Web Interface, because this provides the most effective interface for the features provided. You can deploy Receiver for Java using the sample HTML pages provided with the client package, but this requires more work on your part.

Note: Seamless desktops are not supported.

Seamless Windows

Seamless windows means that each remote application appears in a separate resizable window on the Receiver for Java desktop. Users can resize the application window, minimize it, and copy and paste text between published applications and applications running locally on the user device. Copy/paste also works for non-text objects when used between applications sharing a session.

Note: Seamless windows are supported on Mac OS X Version 10.3 (Panther). However, if Receiver for Java is configured for seamless mode and run on earlier versions of Mac OS X platforms, a non-seamless session is launched.

Dynamic Session Reconfiguration

For seamless windows, Receiver for Java detects and requests the server to update the underlying session size when the local desktop size changes. The receiver cannot detect changes to the local color depth.

Session Sharing

Session sharing allows seamless application launches to share a single connection rather than creating a new connection for each application. This reduces the system overhead and therefore improves response times for users who have several applications open at the same time. Applications launched in existing sessions also launch more quickly, because a new connection and associated resources do not need to be created.

Connection Center

The Connection Center includes a notification area and the **Connections** and **Settings** options.

The notification area is similar to the notification area on computers running Windows. Notification icons appear in the notification area for certain published applications. These icons provide information and access to application settings.

The **Connections** and **Settings** options launch separate dialog boxes.

The **Connections** dialog box allows users to:

- Disconnect a session
- Switch between full screen and seamless mode
- View properties such as the encryption setting and the user name
- Log off a server session
- Close a published application

The **Settings** dialog box allows users to:

- Configure Receiver for Java settings such as general settings, printer and drive mapping, firewall settings, bitmap cache options, and hotkey configuration

Receiver for Java Requirements

To run the Citrix Receiver for Java, the user device must have the following:

- A Web browser with Java 2, Standard Edition Version 1.6.18, configured to accept signed Java applets.
- Network access to the Web server that stores the Receiver for Java files.

Supporting Java Environments

A large number of Java-enabled environments are available, and their functionality varies from platform to platform. To validate proper functionality of the Receiver for Java, Citrix selects a representative group of platforms for testing.

For English and other European languages, Receiver for Java has been tested with Windows Internet Explorer 8 and Firefox 3.5 on:

- Windows 7
- Windows XP Service Pack 3 (Professional and Home Editions)
- Windows Vista

Supporting Citrix Products

Receiver for Java supports the following Citrix products:

- Citrix XenApp 6 for Windows Server 2008 R2
- Citrix XenApp 5 for Windows Server 2008
- Citrix XenApp 5 for Windows Server 2003
- Citrix XenDesktop 4

Deploying the Receiver for Java

To deploy Citrix Receiver for Java, you need:

- A copy of the receiver package. You can download the package from the Citrix Web (<http://www.citrix.com>) site or copy it in decompressed form from the Citrix XenApp installation media. Citrix recommends that you obtain the latest version of the receiver from the Web site.

On the Web site, the receiver package is available in two formats:

- .zip, primarily for Windows systems.
- .tar.gz, primarily for UNIX systems.
Both have identical contents.
- A means of decompressing and unpacking the .zip or .tar.gz package, if you download this from the Web site. If you are copying files from the XenApp installation media you do not need to decompress them.
- Administrator access to a Web server.

Note: If deploying the receiver using the Web Interface, you can configure the receiver deployment options using the Delivery Services Console.

To unpack the Receiver for Java package

1. Copy the Receiver for Java package to a suitable location on the Web server. For Microsoft IIS servers, copy the package to a folder in the Web root directory (typically C:\inetpub\wwwroot). For UNIX systems, consult the Web server documentation.

Note: If you downloaded the compressed package from the Web site, extract the program files from the .zip or .tar.gz package to the same folder, using a suitable decompression utility.

A number of files are created on the Web server. The *N.jar files are signed Java archives that make up the applet.

There are a number of different components:

Essential

Use one of the following components.

Archive File	Approximate Size	Description
JICAEngN.jar	881KB	Complete archive. Contains the contents of all of the other archives apart from cryptojN.jar and sslN.jar, which must be included if required.
JICA-coreN.jar	542KB	Core archive. Provides only a basic connection. You add functionality by using it in conjunction with the other component archives described in the following tables.

Security

Use these components in conjunction with JICAEngN.jar or JICA-coreN.jar, as required.

Archive File	Approximate Size	Description
sslN.jar	30KB	SSL component. Adds SSL and TLS encryption support.
cryptojN.jar	169KB	Encryption component required for ICA encryption. This is not needed for SSL and TLS encryption support.

Optional

Use these components in conjunction with JICA-coreN.jar, as required. They are included in JICAEngN.jar.

Archive File	Approximate Size	Description
JICA-audioN.jar	9KB	Audio component. Adds receiver audio mapping.

To unpack the Receiver for Java package

JICA-browseN.jar	27KB	ICA browsing component. Adds support for ICA browsing and is applicable when deploying the receiver without the Web Interface.
JICA-cdmN.jar	26KB	CDM component. Adds client drive mapping.
JICA-clipboardN.jar	10KB	Clipboard component. Adds receiver clipboard mapping.
JICA-configN.jar	78KB	User configuration component. Adds support for the status bar, buttons, and the ICA Settings dialog box.
JICA-printerN.jar	71KB	Printer component. Adds receiver printer mapping.
JICA-seamlessN.jar	84KB	Seamless and Connection Center components. Adds support for seamless windows and the Connection Center.
JICA-sicaN.jar	17KB	ICA encryption component. Adds ICA encryption support.
JICA-zlcN.jar	98KB	SpeedScreen latency reduction component. Adds support for local text echo and mouse feedback.

Deploying Receiver for Java Through Web Interface

You can deploy Citrix Receiver for Java through Web Interface as a primary delivery mode for use as a fallback if your users are unable to run other receivers.

Because Receiver for Java offers the broadest range of support in terms of user environments, devices, operating systems, and Web browsers, it can be used as a fallback option for scenarios where a native client cannot be used. You can configure the client detection and deployment process to offer Receiver for Java to users who do not have a native client or are unable to download and deploy a receiver from the Citrix XenApp Web site.

You must ensure that Receiver for Java is available in the %Program Files%\Citrix\Web Interface*Version*\Clients\Java directory for the XenApp Web site in order to be able to deploy it to your users. If Web Interface is running on a 64-bit computer, use %Program FILES (x86)\Citrix\Web Interface*Version*\Clients\Java. If you have copied the receiver to this location, Internet Information Services (IIS) must be reset. For directions on resetting IIS, see www.microsoft.com.

Note: In Web Interface 5.0 and earlier, the Java folder was named lcajava.

To configure fallback to Receiver for Java

1. From **Start** menu, click **All Programs > Citrix > Management Consoles > Citrix Web Interface Management**.
2. In the left pane of the Citrix Web Interface Management console, click **XenApp Web Sites** and select your site in the results pane.
3. From the **Action** menu, click **Client Deployment**.
4. For sites that offer only online applications, select **Native client** and click **Properties**.

Note: You do not need to make Receiver for Java available to users in order to provide the fallback functionality.

5. Click **Fallback Behavior**.
6. Specify the circumstances under which users without a native receiver are offered Receiver for Java by choosing one of the following options:
 - If you want users without a native receiver to download and deploy an appropriate Citrix receiver, select **Deploy a native client**. This is the default setting.
 - If you want users without a native receiver to be offered Receiver for Java and only be prompted to download and deploy a native receiver if they cannot use Receiver for Java, select **Deploy a native client and allow user to choose between this and the Client for Java**.
 - If you want users without a native receiver to be prompted to download and deploy an appropriate receiver in addition to being offered Receiver for Java, select **Automatically fall back to the Client for Java**.

Customizing the Receiver for Java Deployment

You can configure the components included in the deployment of Citrix Receiver for Java.

The size of Receiver for Java is determined by the packages you include. The fewer packages selected, the smaller the size (it can be as small as 540 KB). If you want to limit the size of the receiver for users on low bandwidth connections, you can deploy only a minimum set of components. Alternatively, you can allow users to select which components they require.

Note: Some components that you make available in Receiver for Java may require further configuration on users' devices or on the server.

1. In the **Manage Client Deployment** dialog box, select **Native client** or **Client for Java** and **Properties**.
2. Click **Client for Java** to select from the packages described in the following table.

Package	Description
Audio	Enables resources running on the server to play sounds through sound devices installed on users' computers. You can control the amount of bandwidth used by the receiver audio mapping on the server.
Clipboard	Enables users to copy text and graphics between online resources and applications running locally on their devices.
Local text echo	Accelerates the display of the input text on users' devices.
SSL/TLS	Secures communication using Secure Sockets Layer (SSL) and TLS (Transport Layer Security). SSL/TLS provides server authentication, encryption of the data stream, and message integrity checks.
Encryption	Provides strong encryption to increase the privacy of Citrix receiver connections.

Client drive mapping	<p>Enables users to access their local drives from within a session. When users connect to the server, their client drives, such as floppy disks, network drives, and optical drives, are mounted automatically. Users can access their locally stored files, work with them during their sessions, and save them again on a local drive or on a drive on the server.</p> <p>To enable this setting, users must also configure client drive mapping in the Receiver for Java Settings dialog box.</p>
Printer mapping	Enables users to print to their local or network printers from within a session.
Configuration UI	Enables the Receiver for Java Settings dialog box. This dialog box is utilized by users to configure Receiver for Java.

Using Private Root Certificates with Receiver for Java

If you configured Secure Gateway or the SSL Relay service with a server certificate obtained from a private certificate authority (for example, if you issue your own certificates using Microsoft Certificate Services), you must import the root certificate into the Java keystore on each user's device. See the Sun Developer Network (<http://java.sun.com/>) for details about importing certificates into the keystore using the Java keytool.

Getting Started with the Sample HTML Files

Citrix Receiver for Java comes with sample HTML pages that you can customize to specify the correct archives for the user's browser.

Each sample HTML page is described, together with instructions for customizing the page. To use seamless windows and the Connection Center, read the instructions about how to edit `seamless1.html`, but also keep the `desktop.html` instructions close for reference. If you do not want to use this functionality, read the instructions for editing `desktop.html`.

To access the Connection Center, session sharing, and seamless windows functionality, Citrix strongly recommends that you use the Web Interface, which automates the steps that you otherwise need to implement yourself.

Seven sample HTML files are supplied in the receiver package (in the `\Examples` folder):

index.html

This page contains links to and descriptions of the six launching pages:

- **desktop.html**, **application.html**, and **autoproxy.html**. If you do not want to implement seamless windows and the Connection Center, use these pages.
- **seamless1.html**, **seamless2.html**, and **seamless3.html**. To implement seamless windows and the Connection Center, use these pages.

desktop.html

This page launches a desktop session to a server. To make a connection with this page, specify an address for the server.

application.html

This page launches a connection, with 128-bit ICA encryption enabled, to a published application. Specify the name of the published application and the name of a server to use for server location.

autoproxy.html

This page launches a connection to a published application through a proxy server, using proxy auto detection. Specify the name of the published application and the name of a server to use for the server location.

seamless1.html, seamless2.html, and seamless3.html

These pages start remote applications using the Connection Center and seamless windows. The only difference between the three files is that they each start a different application. The applications are launched using an existing ICA session when possible. When session sharing is not possible, a new ICA session is created. You specify the name of a published application and the name of a server to use for the server location.

Customizing the desktop.html File

Desktop.html contains the following <applet> tag:

```
<applet name="javaclient"
  codebase=".."
  code="com.citrix.JICA"
  archive="JICA-coreN.jar,JICA-configN.jar"
  width="640"
  height="480">
  <param name="Address" value="plateau">
  <param name="End" value="end.html">
</applet>
```

The <applet> tag is used to configure the receiver. Some parameters are specified inside the <applet> tag:

Applet name

This is an optional, unique name for the applet. Use this name to refer to the applet when writing scripts. In desktop.html, the applet name javaclient is used by a script that displays a warning message if the user tries to close the Web browser window when an ICA session is running. It is also needed for proxy auto configuration (PAC) file support.

Codebase

The path from the HTML page to the receiver archives. Change this path if it is not correct for your deployment.

Code

The name of the class file that is executed. For the receiver without the Connection Center, this is always com.citrix.JICA.

Archive

Specify signed archives here. Separate multiple archives with commas.

Note: If, for example, you want users to be able to map drives and printers, specify the necessary archives here.

Width

The width of the applet, in pixels.

Height

The height of the applet, in pixels.

All other parameters are specified using <param> tags, located between the <applet> and </applet> tags. Use the <param> tags in the form:

```
<param name="parametername" value="valuenam">
```

where *parametername* is the name of the parameter you are specifying and *valuenam* is the value you are defining.

To customize and use desktop.html

1. Open desktop.html in a plain text editor and find the <applet> tag section:

```
<applet name="javaclient"
  codebase=".."
  code="com.citrix.JICA"
  archive="JICA-coreN.jar,JICA-configN.jar"
  width="640"
  height="480">
  <param name="Address" value="plateau">
  <param name="End" value="end.html">
</applet>
```

This is the section that launches the receiver.

2. Change the Address value to the address of a server on your local network.
3. Change the relative path specified for the codebase if it is not correct for your deployment.
4. Publish the sample HTML pages using your Web server. See the Web server documentation for more information about how to do this.
5. On the user device, open a Web browser and open the URL for the sample HTML pages. The Index.html page opens.
6. Click the link for Minimal Desktop. The applet appears.
7. To connect to the server, click **Connect** or **Click to connect**. To configure the client using the **ICA Settings** dialog box, click **Settings**.

You can edit application.html and autoproxy.html in the same way.

To change the warning message displayed when a user tries to close an active session

If you try to close the Web browser window when using a session created with one of the example Web pages, a warning message appears. The message is defined in this section of the HTML pages:

```
function onBeforeUnload() {
  var connected = document.javaclientname.isConnected();
  if (connected) {
    alerted = true;
    return "Closing this window will disconnect
    your ICA session";
  }
}
```

```
    }  
}
```

where *javaclientname* is the name of the applet.

1. To change the message displayed, edit the text in the HTML pages.

Customizing the seamless1.html File

Seamless1.html contains the following applet tag:

```
<applet name="javaclient"
  code="com.citrix.ConnectionCenter"
  codebase=".."
  archive="JICA-coreN.jar,JICA-browseN.jar,JICA-configN.jar,
  JICA-seamlessN.jar"
  width="330"
  height="140">
  <param name="Address" value="Notepad">
  <param name="InitialProgram" value="#Notepad">
  <param name="HTTPBrowserAddress" value="plateau">
  <param name="TWIMode" value="on">
</applet>
```

The applet tag is similar to that used in desktop.html, with the following differences:

Code

The name of the class file that is executed. For the receiver with the Connection Center, this is always com.citrix.ConnectionCenter.

Archive

The JICA-seamless archive is required for the Connection Center and seamless windows.

Width and height

These are set to 330 and 140 pixels respectively, which are appropriate dimensions for the Connection Center user interface.

TWIMode

This parameter enables seamless windows. Seamless windows are required for session sharing. If you use the Connection Center without seamless windows, there is no session sharing, in other words each application is launched in a separate ICA connection and you gain no reduction in system resource overhead.

You can customize the sample HTML files and specify additional HTML files to launch your own published applications. If you have many applications, it may be easier to provide users with HTML links that all reference a server-side script that generates the <applet> tag as needed, based on the selected link.

To customize and use seamless1.html

1. Open seamless1.html in a plain text editor and find the <applet> tag section:

```
<applet name="javaclient"
  code="com.citrix.ConnectionCenter"
  codebase=".."
  archive="JICA-coreN.jar,JICA-browseN.jar,
  JICA-configN.jar,JICA-seamlessN.jar"
  width="330"
  height="140">
  <param name="Address" value="Notepad">
  <param name="InitialProgram" value="#Notepad">
  <param name="HTTPBrowserAddress" value="plateau">
  <param name="TWIMode" value="on">
</applet>
```

This is the section that launches Citrix Receiver for Java.

2. Change the value of the Address parameter to the name of the published application to which you want to connect.
3. Change the value of the InitialProgram parameter to the application name specified in Address, preceded by a # symbol. For example, if the published application is called Word, use the following parameters:

```
<param name="Address" value="Word">
<param name="InitialProgram" value="#Word">
```

4. Change the relative path specified for the codebase if it is not correct for your deployment.
5. Change the value of the HTTPBrowserAddress parameter to the address of the server used for HTTP browsing.
6. Publish the sample HTML pages using your Web server. See your Web server documentation for more information about how to do this.
7. On the user device, open a Web browser and open the URL for the sample HTML pages. The index.html page opens.
8. Click the **Launch seamless application 1** link. The first time in each Web browser session that you select a seamless link, the Connection Center applet starts, launches an ICA connection to the specified application, and opens it in a separate window. If you select another seamless link while this session is open, the Connection Center applet starts again; however, this new applet is displayed as a progress indicator rather than a duplicate Connection Center, and it closes itself when the new application opens. In this way the launching and management of all applications is centralized by the initial Connection Center instance, which performs session sharing when possible.

9. Select **Connections** to view the **Connections** dialog box. Double-clicking a window node on the Connections tree brings that window to the front. If the window is minimized, double-clicking the node has no effect. Right-clicking a window node displays the application's **System** menu. Closing the **Connection Center** window disconnects all connected sessions, after prompting the user for confirmation.

Using Signed Java Applets

Due to security restrictions imposed by Java, many Java environments do not permit users to connect to other computers on the network when using Java applets.

When a Java applet attempts to make a connection to the server specified in the HTML page, the Java security manager detects the attempt to connect to another computer and cancels the operation. The result of this security restriction is that, under normal conditions, a user device can connect to a server only if the server is also the same device as the Web server that contains the applet class files.

To overcome this restriction, Citrix Receiver for Java uses signed archives. The signature confirms that the files being downloaded came from Citrix and have not been altered since the signature was applied. You must ensure that users' Web browsers are configured to accept signed Java applets.

When attempting a connection to the server, the user is prompted with the Citrix signed certificate. When the user accepts the signature, the connection is permitted.

Example: To make a desktop for a server available to users

In the following example, you want to make the desktop for a server called "buster" available to users. Buster is a XenApp server that runs Microsoft IIS. You want the users to be able to use the drives on their user devices during sessions, and to be able to print to local or network printers.

1. From the Citrix Web site, download JICAComponents.zip to C:\inetpub\wwwroot on buster.
2. Extract the files to C:\inetpub\wwwroot.
3. In the Examples folder, open Desktop.html using Notepad, then make and save the following changes:

- a. To specify the correct server, change the value of the Address parameter as follows:

```
<param name="Address" value="buster">
```

- b. To enable users to map drives and printers on their devices, add **JICA-cdmN.jar** and **JICA-printerN.jar** to the **Archive** attribute, so that it reads as follows:

```
archive="JICA-coreN.jar,JICA-configN.jar,  
JICA-cdmN.jar,JICA-printerN.jar"
```

4. Verify that the users' Web browsers are configured to accept signed Java applets.
5. Publish desktop.html using the IIS Manager tool, and tell the users the URL of the page (<http://buster/desktop.html>).

Configuring the Receiver for Java

Citrix Receiver for Java can be configured using:

- An HTML page.
- The **ICA Settings** dialog box.

To display the **ICA Settings** dialog box, click the **Settings** button. In seamless mode, the **Settings** button is on the Connection Center. If the receiver is not in seamless mode, the **Settings** button is on the status bar.

You can prevent users from configuring their own settings by removing the **Settings** button or the status bar, as described in [Status Bar and Settings Button](#).

- The Web Interface.

The Web Interface automatically generates the necessary Web pages to launch the receiver. See [Web Interface](#) for details about how to use the Web Interface to configure the receiver

Note: You can only configure drive mapping through the **ICA Settings** dialog box. You cannot configure drive mapping on an HTML page or through the Web Interface because this is a violation of receiver security.

To set the receiver language

Citrix Receiver for Java allows you to specify which language is used to display the user interface. By default, a session uses the language specified for the user device to display the user interface. If you specify a language code that is not recognized or not supported, English is used.

1. Specify the following parameter in the HTML page:

```
<param name="Language" value="yourlanguage">
```

where *yourlanguage* is the two-letter abbreviation for the language you want to use.

The standard two-letter abbreviations are:

- English = en
- French = fr
- German = de
- Spanish = es
- Japanese = ja

For example, to use Japanese as the language on a non-Japanese device when connecting to the server named CitrixServer, create an applet tag:

```
<applet code="com.citrix.JICA"  
  archive="JICAEngN.jar"  
  width="1024" height="768">  
  <param name="Address" value="CitrixServer">  
  <param name="Language" value="ja">  
</applet>
```

If you use languages other than English, ensure that your Web server sends HTML files with the correct Content-Type and Charset, to avoid possible corruption of the applet parameter strings. Configuration details depend on the server software in use.

When troubleshooting suspected problems with parameter string encoding, copy the strings outside the applet tag and check that they display correctly in the Web browser.

To change the network protocol for the Receiver for Java

The network protocol setting allows you to control the way Citrix Receiver for Java searches for servers and how it communicates with them.

The protocols are:

TCP/IP + HTTP

The receiver uses the HTTP protocol to search for servers. The receiver communicates with the server using ICA protocol over TCP/IP. This is the default protocol.

SSL/TLS + HTTPS

The receiver uses the HTTPS protocol to search for a list of servers. The receiver communicates with the server using the SSL or TLS protocols.

1. To change the protocol to SSL/TLS+HTTPS, add the following parameter to the HTML page:

```
<param name= "SSEnable" value="on">
```

Configuring Server Browsing

Server browsing is the mechanism by which Citrix Receiver discovers an appropriate server to host a given application. Depending on the server configuration, this can involve taking load balancing into account so that the user's application is run on the least loaded server.

The default browser server address is ica. You must set specific server addresses for XenApp computers unless your networking environment is configured with a DNS record for ica. The receiver uses the HTTP or HTTPS protocol respectively to contact the servers.

Example: Specifying the Browser Server

In the following example, the HTTPBrowserAddress parameter is specified to be the server Wizard. This browser server is responsible for locating an appropriate server to run the published application Notepad.

```
<html>
  <body>
    <applet code="com.citrix.JICA"
      archive="JICAEngN.jar"
      width="640" height="480"
      <param name="HTTPBrowserAddress" value="Wizard">
      <param name="Address" value="Notepad">
      <param name="InitialProgram" value="#Notepad">
    </applet>
  </body>
</html>
```

Note: If you are using the JICA-coreN.jar archive, you must specify the JICA-browserN.jar archive to enable server browsing.

To specify a business recovery server group

Business recovery provides consistent connections to published applications in the event of a browser server disruption. You can define up to three groups of servers to which you want to connect: a primary and two backups. Each group can contain from one to five servers.

1. Use the following parameters to specify server groups:

- HTTPBrowserAddress and HTTPBrowserAddress2 through HTTPBrowserAddress5 specify the primary group of servers
- HTTPBrowserAddress6 through HTTPBrowserAddress10 specify the first backup group of servers
- HTTPBrowserAddress11 through HTTPBrowserAddress15 specify the second backup group of servers

Fill in any unused server addresses with five dashes (-----). These dashes are required to fill in any gaps in the list but are not required at the end of the list.

Example: Specifying a business recovery server group

In the following example, the primary group of servers contains Arthur, Morgana, and Merlin. The first backup group contains the servers Excalibur and Stone. There is no secondary backup group.

```
<html>
  <body>
    <applet code="com.citrix.JICA"
      archive="JICAEngN.jar"
      width="640" height="480">
      <param name="HTTPBrowserAddress" value="Arthur">
      <param name="HTTPBrowserAddress2" value="Morgana">
      <param name="HTTPBrowserAddress3" value="Merlin">
      <param name="HTTPBrowserAddress4" value="-----">
      <param name="HTTPBrowserAddress5" value="-----">
      <param name="HTTPBrowserAddress6" value="Excalibur">
      <param name="HTTPBrowserAddress7" value="Stone">
    </applet>
  </body>
</html>
```

To change the client name

The *client name* is used to identify Citrix Receiver for Java to the server, and is also used to name printers. You may need to change the client name if you are trying to access resources shared with another receiver with the same name.

By default, the receiver uses the value for the user device's host name (if it exists and is not set to localhost) as the client name reported to the server. If the receiver cannot use the user device's host name, it uses AnonJava as the client name. The client name sent to the server is always truncated to 20 characters.

You can change the client name on the HTML page.

1. To change the client name, add two parameters on the HTML page:

```
<param name="client.wfclient.UseHostname" value="off">  
<param name="client.wfclient.Clientname" value="yourclient">
```

where *yourclient* is the client name you want to use.

Passing Parameters to Applications

When connecting to a published application, specify the application name using the InitialProgram parameter on the HTML page. For example, to connect to an application called Notepad, specify the following parameters:

```
<param name="Address" value="Notepad">  
<param name="InitialProgram" value="#Notepad">
```

The parameters that an application honors are built into the application and do not have to be file names.

To pass a parameter to an application

1. Specify the following parameters on the HTML page:

```
<param name="Address" value="application">  
<param name="InitialProgram" value="#application">  
<param name="Param" value="parameter">
```

where *application* is the name of the published application and *parameter* is the parameter. You can specify a maximum value length of 256 characters for these parameters. For example, to open a file called M:\New.txt in Notepad, specify the following parameters:

```
<param name="Address" value="Notepad">  
<param name="InitialProgram" value="#Notepad">  
<param name="Param" value="M:\new.txt">
```

Note: For parameter passing to work, you must configure the published application to receive parameters by appending %* to the published application's command line. For example:

```
notepad %*
```

File name parameters are interpreted by the remote application relative to the server's file system. If you want to pass a file from the user device to a remote published application, you must use user device drive mapping.

To set the size and number of colors used for the session window

Just as you can set the dimensions of the applet panel in which sessions run using the Width and Height attributes of the <applet> tag, you can also specify the size of the remote session by using the DesiredHRes and DesiredVRes parameters. If you do not specify these last two parameters, the remote session fits into the applet area available when any border and status bar are added.

The number of colors used in the session window is defined with a parameter on the HTML page.

1. Specify the following parameter in the HTML page:

```
<param name="DesiredColor" value="2|4|8">
```

where 2 specifies 256 colors, 4 specifies thousands of colors, and 8 specifies millions of colors. You cannot configure the receiver to use only 16 colors, but it can display applications published in 16 color mode; these are run in 256 colors.

Showing and Hiding the Status Bar and Settings Button

You can display or hide the status bar and **Settings** button using parameters on the HTML page. Both are displayed by default; however, if you do not want users to make configuration changes, you may hide the **Settings** button. If you decide that maximum screen real estate is a priority, you may hide the status bar.

When the receiver is in seamless mode, the status bar is not visible and the user accesses the **Settings** dialog box from the Connection Center.

To hide the status bar

1. Specify the following parameter on the HTML page:

```
<param name="ShowStatusBar" value="no">
```

To hide the Settings button

1. Specify the following parameter on the HTML page:

```
<param name="ShowSettingsButton" value="no">
```

Note: To display the **Settings** button and status bar when using the component archives, you must include the JICA-config archive. This functionality is included in the complete archive.

To enable Session Reliability

Session Reliability enables sessions to remain open and on the screen when network connectivity is interrupted, therefore allowing Citrix Receiver for Java users to view the application until the network connection is restored. This feature is especially useful for mobile users with wireless connections.

For session reliability and SSL support through Secure Gateway, Secure Gateway Version 3 is required.

1. Specify the following parameter on the HTML page:

```
<param name="CGPAddress" value="hostname:port">
```

Rather than specifying the hostname, type an asterisk (*) to use the Address parameter value as the host (session reliability server).

The port value is optional. If you do not specify a port value, the default 2598 is used. If a connection on port 2598 fails, the receiver tries to establish a standard (non-session reliability) connection on port 1494.

Controlling Auto-Reconnect and Session Termination

You can control how Citrix Receiver for Java behaves when starting or ending a session by specifying parameters on the HTML page.

Note: The information in this topic does not apply if you are using the Connection Center. Sessions always start automatically and, if the network connection is lost, an attempt is always made to reconnect.

To change how Receiver for Java connects to the server

1. Specify the following parameter on the HTML page:

```
<param name="Start" value="Manual|Auto">
```

If you set this parameter to **Manual** (the default), the user must click to connect to a server. If you set it to **Auto**, the message "Connecting to server" appears as the HTML page is displayed and the user is automatically connected to the server. If no parameter is identified, the default is used.

To change what happens when a session ends

1. Specify the following parameter on the HTML page:

```
<param name="End" value="Manual|Auto|Terminate|URL">
```

where:

- **Manual** displays the startup splash screen when the session ends, and the message "Connection Terminated - Click to connect." To reconnect, the user clicks anywhere on the splash screen.
- **Auto** displays the **Reconnecting** dialog box when the session ends for any reason. The number in the dialog box counts down to 0 and the client reconnects.
- **Terminate** displays either "Connection Terminated" or "Connection Error" when the session ends, depending on whether the user chose to end the session or whether or not there is a problem that caused the session to end.
- **URL** displays the splash screen and redirects in two seconds to the specified URL. You can specify the URL of any Web page.

The HTML examples supplied with the receiver include the End parameter. The value specified is a URL to a page called End.html. The applet tag section of each of the examples has this parameter:

```
<param name="End" value="end.html">
```

When you end the session, the receiver redirects to end.html, which contains a script to close the browser window. You can edit end.html to customize it.

To change the time-out period for automatic reconnection

The default time-out period is five seconds.

1. Specify the following parameter on the HTML page:

```
<param name="ReconnectDelay" value="delay">
```

where *delay* is the delay in seconds. Specifying this parameter does not affect the delay before connection to an HTML page if you specified a URL for the End parameter.

Note: If the Start and End parameters are both set to Auto, the startup splash screen is displayed and you must click on it to connect.

Specifying Keyboard and Mouse Preferences

The Citrix Receiver for Java lets you specify what type of keyboard to use in sessions. By default, if you do not specify a keyboard preference, the session uses the default layout for the connected XenApp server. The receiver supports the use of any keyboard supported by the server to which the user is connecting.

When using the Receiver for Java with applications that require a 3-button mouse, the middle button of a 3-button mouse can be emulated by clicking both buttons of a 2-button mouse at the same time.

To specify a keyboard other than the server's default

1. Specify the following parameter on the HTML page:

```
<param name="user.wfclient.keyboardlayout" value="layout">
```

where *layout* is a value from the server's list of supported keyboards. A list of the supported keyboards is provided in [Supported Keyboard Layouts](#).

For example, to specify a Danish keyboard, create an HTML page like the following:

```
<html>
  <body>
    <applet code="com.citrix.JICA"
      archive="JICAEngN.jar"
      width="640" height="480">
      <param name="Address" value="CitrixServer">
      <param name="user.wfclient.keyboardlayout"
        value="Danish">
    </applet>
  </body>
</html>
```

The receiver supports the following keyboard types to distinguish between subtypes of the Japanese keyboard layout:

```
"(Default)"
"IBM PC/XT or compatible keyboard"
"101 Keyboard (Japanese)"
"106 Keyboard (Japanese)"
"NEC PC-9800 on PC98-NX (Japanese)"
"NEC PC-9800 on PC98-NX 2 (Japanese)"
"NEC PC-9800 Windows 95 and 98 (Japanese)"
"NEC PC-9800 Windows NT (Japanese)"
"Japanese Keyboard for 106 (Japanese)"
"DEC LK411-JJ Keyboard (Japanese)"
"DEC LK411-AJ Keyboard (Japanese)"
```

Note: If you are using a 109 key Japanese keyboard, specify the keyboard type as 106 Keyboard (Japanese).

To specify a Japanese keyboard type

1. Specify the following parameter on the HTML page:

```
<param name="user.wfclient.keyboardtype"  
value="101 Keyboard (Japanese) | 106 Keyboard (Japanese)">
```

For example, to specify a Japanese 106 key keyboard, create an HTML page like the following:

```
<html>  
  <body>  
    <applet code="com.citrix.JICA"  
      archive="JICAEngN.jar"  
      width="640" height="480">  
      <param name="Address" value="CitrixServer">  
      <param name="user.wfclient.keyboardtype"  
        value="106 Keyboard (Japanese)">  
    </applet>  
  </body>  
</html>
```

Supported Keyboard Layouts

The supported keyboard layouts are:

"(Server Default)"

"Albanian" "Belarusian"

"Belgian Dutch"

"Belgian French"

"Brazilian (ABNT)"

"British"

"Bulgarian (Latin)"

"Bulgarian"

"Canadian English (Multilingual)"

"Canadian French (Multilingual)"

"Canadian French"

"Croatian"

"Czech (QWERTY)"

"Czech"

"Danish"

"Dutch"

"Estonian"

"Finnish"

"French"

"German (IBM)"

"German"

"Greek (220) Latin"

"Greek (220)"

"Greek (319) Latin"

Supported Keyboard Layouts

"Greek (319)"
"Greek Latin"
"Greek"
"Hungarian 101-Key"
"Hungarian"
"Icelandic"
"Irish"
"Italian (142)"
"Italian"
"Japanese (client and server IME)"
"Japanese (client IME only)"
"Japanese (server IME only)"
"Korean" "Latin American"
"Latvian (QWERTY)"
"Latvian"
"Lithuanian"
"Norwegian"
"Polish (214)"
"Polish (Programmers)"
"Portuguese"
"Romanian"
"Russian (Typewriter)"
"Russian"
"Serbian (Cyrillic)"
"Serbian (Latin)"
"Slovak (QWERTY)"
"Slovak"
"Slovenian"

Supported Keyboard Layouts

"Spanish Variation"

"Spanish"

"Swedish"

"Swiss French"

"Swiss German"

"Taiwan"

"Turkish (F)"

"Turkish (Q)"

"Ukrainian"

"United Kingdom"

"US"

"US-Dvorak for Right hand"

"US-Dvorak for left hand"

"US-Dvorak"

"US-International"

Specifying Japanese IME Preferences

Citrix Receiver for Java provides a choice of options for using a Japanese Input Method Editor (IME). Users can configure these options using the **ICA Settings** dialog box. Alternatively, you can set the keyboard layout parameter in the <applet> tag; this overrides the users' settings.

You can choose between using an IME on the user device or an IME on the server.

With an IME on the user device, users can choose their preferred IME that they have installed and they do not have to deal with one IME for local applications and another potentially different IME with a different dictionary for server-side applications. When using an IME on the user device, the user composes the text in a separate window instead of at the insertion point.

With an IME on the server, the user composes the text at the insertion point.

To use an IME on the user device for connections to servers running Windows Server 2003

1. Specify the following parameter on the HTML page:

```
<param name="user.wfclient.keyboardlayout"  
value="Japanese (client IME only)">
```

To use a server-side IME

1. Specify the following parameter on the HTML page:

```
<param name="user.wfclient.keyboardlayout"  
value="Japanese (server IME only)">
```

Specifying Hotkey Functions

Hotkeys are used to control the behavior of Citrix Receiver for Java and as substitutes for the standard Windows hotkeys. For example, to display the Windows Security Desktop on a Windows computer, press CTRL+ALT+DEL. If you are running the receiver on a Windows computer and are working in a XenApp session, this key combination opens the Security Desktop on the local device. Hotkey functionality allows you to map common key combinations like CTRL+ALT+DEL to a key combination such as CTRL+F1 that is ignored by your local operating system. When you press this new combination, the receiver sends CTRL+ALT+DEL to the server, displaying the Windows Security Desktop in your session.

You can specify hotkeys on the HTML page or the user can do it by using the **ICA Settings** dialog box.

Receiver hotkeys use a pair of keys. The first is a modifier key and the second is a character. The following hotkeys are available:

Hotkey (Default Mapping)	Description
Hotkey2 (Shift+F3)	Close Remote Application. The Close Remote Application hotkey disconnects applications opened in an session. If no programs are open, the session is disconnected after the user is prompted for confirmation.
Hotkey3 (Shift+F2)	When the receiver is running in seamless mode, this hotkey toggles between seamless mode and <i>windowed mode</i> . When the receiver is not in seamless mode, this hotkey is used when a reconnected session is larger than the applet panel; it toggles between embedding the session inside the applet panel with scroll bars and displaying it in a separate window. When the receiver is running in full screen mode, this hotkey toggles the title bar on and off.
Hotkey4 (CTRL+F1)	Substitute for the standard Windows hotkey CTRL+ALT+DEL. The CTRL+ALT+DEL hotkey displays the Windows Security Desktop in the session.
Hotkey5 (CTRL+F2)	Substitute for the standard Windows hotkey CTRL+ESC. On XenApp computers, the remote Windows Start menu appears.
Hotkey6 (ALT+F2)	Substitute for the standard Windows hotkey ALT+ESC. This hotkey brings the focus to maximized and minimized windows of programs that are open in a session, in the order that they were opened.
Hotkey7 (ALT+PLUS SIGN)	Substitute for the standard Windows hotkey ALT+TAB. This hotkey cycles through applications that are open in the session. A popup box appears and displays the programs as you cycle through them. The chosen application receives keyboard and mouse focus.

Specifying Hotkey Functions

Hotkey8 (ALT+MINUS SIGN)	Substitute for the standard Windows hotkey ALT+SHIFT+TAB. Like the ALT+TAB hotkey, this key sequence cycles through applications that are open in the session but in the opposite direction. The chosen application receives keyboard and mouse focus.
Hotkey9 (CTRL+F3)	Substitute for the standard Windows hotkey CTRL+SHIFT+ESC. This hotkey displays the Task Manager.
Hotkey10 (CTRL+F5)	Toggle SpeedScreen latency reduction. This hotkey toggles mouse click feedback and local text echo on and off.
Hotkey 11 (ALT+*)	This hotkey displays the ICA Settings dialog box.

To change the hotkey sequence from the default

1. For each hotkey, specify two parameters on the HTML page: one for the shift state and a second for the character state, as follows:

```
<param name="user.wfclient.hotkey*shift" value="shiftstate">
<param name="user.wfclient.hotkey*char" value="character">
```

where asterisk (*) is the hotkey number; *shiftstate* is CTRL, SHIFT, ALT, or (none); and *character* can be any of the following keys:

- F1 through F12
- TAB
- * (asterisk)
- PLUS SIGN
- MINUS SIGN
- ESC
- (none)

Specifying (none) for the character disables the hotkey.

The following example describes how to map the Close Remote Application hotkey to the key sequence CTRL+F1 and the ALT+TAB hotkey key sequence to Shift+TAB.

```
<html>
  <body>
    <applet code=com.citrix.JICA
      archive="JICAEngN.jar"
      width=640 height=480>
      <param name="Address" value="CitrixServer">
      <param name="user.wfclient.hotkey2shift" value="ctrl">
      <param name="user.wfclient.hotkey2char" value="f1">
      <param name="user.wfclient.hotkey7shift" value="shift">
      <param name="user.wfclient.hotkey7char" value="tab">
    </applet>
  </body>
</html>
```

Note: There may be conflicts between the default or user-defined receiver hotkeys and those pre-configured on Mac OS X and UNIX platforms. See your platform documentation for further information.

User Device Mapping

Citrix Receiver for Java supports user device mapping for connections to servers. User device mapping allows a remote application running on the server to access printers and disk drives attached to the local user device. The applications and system resources appear to the user at the user device as if they are running locally. Ensure that user device mapping is supported on your server before using these features.

Client Drive Mapping

Client drive mapping can make any specified directory on the user device available to the user during sessions. When a server is configured to allow client drive mapping, users can access their locally stored files, work with them during their sessions, and then save them again either on a local drive or on a drive on the server.

The user's home directory is automatically mapped at the start of a session. Only the home directory is mapped automatically. All other directories must be configured manually. Users can configure drive mapping using the **Drive Mapping** tab on the **ICA Settings** dialog box.

When drive mapping is configured, the receiver attempts to use it for all connections. If the server does not support drive mapping, or if the Java environment is configured not to allow access to local drives, drive mapping is not available.

Note: When drive mapping is enabled and the receiver accesses a mapped drive for the first time, a dialog box appears on the user device. The dialog box informs the user that the receiver is attempting to access a mapped drive and the user must click **Yes** to allow the receiver to access the drive.

Drive mapping can be configured only by the user through the **ICA Settings** dialog box. Configuration settings are stored in the Appsrv.ini file. You cannot configure client drive mapping on an HTML page or through the Web Interface because this is a violation of the receiver's security.

To make client drive mapping available to users when using the core archives, you must include the JICA-cdm archive. If you do not, the **Drive Mapping** tab does not appear in the **ICA Settings** dialog box.

To deploy client drive mapping settings to multiple users, you can configure client drive mapping on one device and copy the Appsrv.ini file to the correct location on the users' devices.

Limitations of Mapped Drives

Once configured, mapped drives are transparent and appear the same as other network drives on the server. However, due to the way Java accesses file systems, the following functions are not available on mapped drives:

- Locking files that are in use by an application. To prevent file corruption, warn users not to access the same file with two or more applications at the same time.
- Setting file attributes.
- Setting date and time on files created or edited on mapped drives.
- Reporting drive capacity and usage. Users must use the operating system of their local computer to determine the capacity of mapped drives.

Mapping Receiver Printers

Printers are auto-detected by default. To make Citrix Receiver for Java printer mapping available to users, specify the JICA[®]printer archive in the <applet > tag or use the full archive. If you do not, the Printer Mapping functionality is not available and the relevant tab does not appear in the **ICA Settings** dialog box.

Note: Printers are not auto-detected on Mac OS X platforms. You can configure printers manually using the **ICA Settings** dialog box (described in the online help).

Detecting Printers Automatically

The receiver automatically detects all printers available to the user device, including USB printers, and makes them available to the session.

Note: Mac OS X provides a J2SE 1.4.x environment but does not provide the Java Print Service API, so printers are not auto-detected.

For PostScript-capable printers, a generic Postscript driver is configured on the server, and the resulting PostScript output is sent directly to the printer.

For non-PostScript printers, the Universal Print Driver (UPD) is configured which encapsulates print jobs in Printer Control Language 4 (PCL4) format. A receiver-based interpreter renders the print job using the user device's local print driver and printing services.

To modify printer settings, users select the **Printer Mapping** tab on the **ICA Settings** dialog box. If a print job requires color or advanced printing options such as duplex printing, users should configure an appropriate native driver. If they configure both a native driver and a UPD driver, the server uses the native driver if it is available; otherwise, it uses the UPD driver.

Users cannot delete auto-detected printers unless the Java environment detects that they are no longer available.

ICAPrinterDrivers.txt File

The contents of the default ICAPrinterDrivers.txt file are as follows:

HP LaserJet
HP DeskJet
HP OfficeJet
HP LaserJet Series II
HP LaserJet III
HP LaserJet 4
HP LaserJet 5
HP LaserJet 4000 Series PCL
HP LaserJet 4000 Series PS
HP LaserJet 4050 Series PCL
HP LaserJet 4050 Series PS
HP LaserJet 5000 Series PCL
HP LaserJet 5000 Series PS
HP LaserJet 8000 Series PCL
HP LaserJet 8000 Series PS
HP LaserJet 8100 Series PCL
HP LaserJet 8100 Series PS
Canon Bubble-Jet BJC-70
Canon Bubble-Jet BJ-200ex
Canon Bubble-Jet BJC-600
Canon LBP-4Canon LBP-8II
Canon LBP-8III
Epson Stylus Pro ESC/P 2
Epson Stylus COLOR ESC/P 2
Epson Stylus Photo ESC/P 2
Epson EPL-3000
Epson EPL-4000
Epson EPL-5000
Epson EPL-6000
Epson EPL-7000
Epson EPL-8000
Epson EPL-9000
Lexmark Optra

To configure printers manually

When you configure printers manually users find those printers mapped to their sessions and ready for use when they log on. When they log off, their printer mappings are deleted from the server. The printers are automatically mapped again the next time they log on.

Note: You cannot configure USB printers manually.

1. Specify the printer name, the port name, and the driver, using the following parameters in the HTML page:

```
<param name="user.localclientprinters" value="printername">  
<param name="user.printername.port" value="portname">  
<param name="user.printername.driver" value="drivername">
```

where:

printername

The name by which you want to identify the printer.

portname

Specifies a file name, port name, or printer IP address (or network name and print queue).

drivername

Specifies the printer driver. This name is case-sensitive and must exactly match the driver name on the server.

Note: When mapping printers attached to a Macintosh computer, you can specify only a file name, not a port name or printer IP address.

When printing to a file, the output file is composed of printer machine code. This file can be sent to a printer using a platform-specific utility. For example, use a command prompt on Windows platforms to send the file to a printer by copying the file to a printer port.

When printing to a port, specify the port. A typical port on Windows systems is LPT1. On Linux or UNIX systems, the port is similar to `/dev/lp0`. Check your operating system documentation for more information.

When printing to a network printer, specify the printer's IP address or network name and print queue (*ipaddress:printqueuname* or *networkname:printqueuname*).

To check the driver list on a server

1. From the **Start** menu, click **Devices and Printers**.
2. Click **Add a printer**.
3. In the **Add Printer** wizard, click **Add a network, wireless or Bluetooth printer**.

The list under **Printers** contains the printer driver names.

To assign a default printer for a session

1. Specify the following parameter:

```
<param name="user.printername.comment" value="WFCDefault">
```

where *printername* is the name of the printer. If the server is set to connect only to the user's default printer, this sets the manually configured printer to be the default printer.

Note: The server must have the correct printer driver installed, as specified either in the **ICA Settings** dialog box or on the HTML page using the Driver parameter. If the correct driver is not installed, the printer is not configured. In this case, you must install the correct printer driver on the server.

You can change the list of drivers that appears in the **ICA Settings** dialog box by editing the ICAPrinterDrivers.txt file. This plain-text file is included in the Citrix Receiver for Java package and is located in the same directory as the receiver archives.

When editing the ICAPrinterDrivers.txt file, add or remove driver names by deleting or adding names to the file, one driver name per line. You can add the driver names in any order.

Examples of Configuring Printers Manually

The following examples demonstrate configuring a printer by specifying parameters on the HTML page.

Example: Manually Configuring Individual Printers

This HTML page is suitable for use only with a Windows-based user device. In this example, the printer's name is LocalPrinter1. It is connected to the receiver's LPT1 port and has a driver named HP LaserJet.

```
<html>
  <body>
    <applet code="com.citrix.JICA"
      archive="JICAEngN.jar"
      width="640" height="480">
      <param name="Address" value="CitrixServer">
      <param name="user.localclientprinters"
        value="LocalPrinter1">
      <param name="user.LocalPrinter1.port" value="lpt1:">
      <param name="user.LocalPrinter1.driver"
        value="HP LaserJet">
    </applet>
  </body>
</html>
```

In this example, the printer's name is NetPrinter1 and has a driver named HP LaserJet. The printer is a network printer that exists on a network print server with an IP address of 192.168.1.24 and a print queue named FLOOR2_LJ.

```
<html>
  <body>
    <applet code="com.citrix.JICA"
      archive="JICAEngN.jar"
      width="640" height="480">
      <param name="Address" value="CitrixServer">
      <param name="user.localclientprinters"
        value="NetPrinter1">
      <param name="user.NetPrinter1.port"
        value="192.168.1.24:FLOOR2_LJ">
      <param name="user.NetPrinter1.driver"
        value="HP LaserJet">
    </applet>
  </body>
</html>
```

Example: Manually Configuring Multiple Printers

This example shows how you would configure two individual printers. Note how the two printer names, LocalPrinter1 and NetPrinter1, are both specified in the user.localclientprinters parameter.

```
<html>
  <body>
    <applet code="com.citrix.JICA"
      archive="JICAEngN.jar"
      width="640" height="480">
      <param name="Address" value="CitrixServer">
      <param name="user.localclientprinters"
        value="LocalPrinter1,NetPrinter1">
      <param name="user.LocalPrinter1.port" value="lpt1:">
      <param name="user.LocalPrinter1.driver"
        value="HP LaserJet">
      <param name="user.NetPrinter1.port"
        value="192.168.1.24:FLOOR2_LJ">
      <param name="user.NetPrinter1.driver"
        value="HP LaserJet 400 Series PS">
    </applet>
  </body>
</html>
```

To enable receiver audio mapping

Citrix Receiver for Java audio mapping enables applications running on the server to play sounds through a sound device installed on the user device. To make receiver audio mapping available to users, you must enable it using a parameter on the HTML page.

Important: Starting the receiver while an audio application is running on your desktop can disable audio mapping. Do not run audio applications while starting the receiver

To make receiver audio mapping available to users, specify the JICA[®]audio archive in the <applet > tag or use the full archive. If you do not, the Audio Mapping functionality is not available.

1. Add the following parameter to the HTML page:

```
<param name="ClientAudio" value="on">
```

You control the amount of bandwidth used by receiver audio mapping by configuring the ICA Audio policy settings on the Delivery Services Console.

Note: If audio is set to use **Low - for low-speed connections**, receiver audio mapping for the user device is disabled.

Connecting Through a Proxy Server

The Citrix Receiver for Java supports both SOCKS and Secure proxy protocols.

Configure the receiver to work with a proxy server by specifying parameters on the HTML page, through the **ICA Settings** dialog box, or through the Web Interface.

Some proxy servers require authentication when a connection is requested. Specify a proxy logon name and password on the HTML page when configuring the receiver. If authentication is required and you do not specify the details on the HTML page, users are prompted to enter the proxy logon name and password when they open a connection.

Note: The receiver supports Basic proxy authentication and NTLM proxy authentication when connecting to a Secure proxy, and user name/password authentication when connecting to a SOCKS proxy. Proxy authentication therefore does not work with proxy servers configured to use other authentication schemes such as Kerberos and Digest.

Microsoft ISA Server

If your deployment includes a Microsoft ISA Server note that, by default, Microsoft ISA Server forbids client connections to Citrix XenApp on ports 1494 and 2598. Modify the Microsoft ISA Server settings as detailed in the Citrix Knowledge Base article: [Configuring Microsoft ISA Server to Allow Outbound ICA Connections \(CTX104998\)](#).

NTLM Proxy Authentication

NTLM proxy authentication is supported when the receiver is configured to access XenApp through a proxy server. The receiver must be running on Windows, connecting through a proxy server that supports NTLM (such as Microsoft Internet Security & Acceleration Server).

To enable proxy auto detection

Proxy auto detection obtains proxy details from the local Web browser settings. It is useful if you are deploying Citrix Receiver for Java in an organization with many proxy servers or if you cannot determine which proxy server will be used when you configure the receiver. Proxy auto detection can be used with:

- Internet Explorer 8.0 or later for Windows using Java SE Runtime Environment (JRE) 6 Update 18.
 - Firefox 3.5
1. Specify the following parameter in the HTML file:

```
<param name="ProxyType" value="auto">
```

To obtain the proxy server settings from a PAC file

A PAC file is a JavaScript file that is served from a local Web server and used to automatically configure the proxy settings of Web browsers. You cannot specify this method of proxy configuration through the **ICA Settings** dialog box.

1. Specify the following parameters in the HTML file:

```
<param name="ProxyType" value="script">  
<param name="ProxyAutoConfigURL"  
  value="http://webserver.example.com/myproxies.pac">
```

where `http://webserver.example.com/myproxies.pac` is the URL for the PAC file.

To specify the proxy server details manually

If you are configuring the proxy manually, confirm the proxy server details with your security administrator. ICA connections cannot be made if these details are incorrect.

1. Specify the following details using parameters in the HTML file:
 - The address of the proxy server.
 - The port number of the proxy server (if not 1080 for SOCKS or 8080 for Secure proxy).
 - The protocol of the proxy server: SOCKS proxy or Secure proxy.
 - In the case of a SOCKS proxy, the protocol version number. Alternatively, you can omit the version number; Citrix Receiver for Java then tries SOCKS Version 5 and fall back to SOCKS Version 4 if necessary.

To enable proxy auto detection

- If the proxy requires authentication and you are supplying it through the HTML page, the proxy logon name and password.

Parameter	Description
ProxyType= <i>none</i> <i>auto</i> <i>socks</i> <i>socksv4</i> <i>socksv5</i> <i>secure</i> <i>script</i>	none No proxy auto Use the Web browser's settings socks Use SOCKS and automatically detect the version socksv4 Use SOCKS Version 4 socksv5 Use SOCKS Version 5 secure Use Secure proxy script Use a PAC file (specified by ProxyAutoConfigURL)
ProxyHost= <i>address:port</i>	Address and port (if required) of the proxy server
ProxyUsername	Proxy username
ProxyPassword	Proxy password
ProxyExcludeList= <i>address1; address2; etc...</i>	A semicolon-separated list of addresses of servers that the client must connect to directly—not through the proxy server.
ProxyAutoConfigURL	The URL for the PAC file. Use with the parameter ProxyType.

Integrating the Receiver with the Secure Gateway or SSL Relay

You can integrate Citrix Receiver for Java with the Secure Gateway or with an SSL relay service. The receiver supports both SSL and TLS protocols:

- SSL provides strong encryption to increase the privacy of your ICA connections and certificate-based server authentication to ensure that the server you are connecting to is a genuine server.
- TLS is the latest, standardized version of the SSL protocol. The Internet Engineering Taskforce (IETF) renamed it TLS when they took over responsibility for the development of SSL as an open standard. TLS secures data communications by providing server authentication, encryption of the data stream, and message integrity checks. Because there are only minor technical differences between SSL Version 3.0 and TLS Version 1.0, the certificates you use for SSL in your XenApp installation also work with TLS. Some organizations, including US government organizations, require the use of TLS to secure data communications.

To enable SSL and TLS

SSL and TLS are configured in the same way, use the same certificates, and are enabled with the same parameter. You configure SSL and TLS using parameters on the HTML page or with the Web Interface.

When SSL and TLS are enabled, each time you initiate a connection Citrix Receiver for Java tries to use TLS first, then tries SSL. If it cannot connect with SSL, the connection fails and an error message appears. You can force receivers to connect only with TLS. The comprehensive set of root certificates stored in the Java plug-in keystore is automatically used. Where the user device is running Microsoft Windows, Microsoft Internet Explorer, and Java 1.6.16, the receiver also uses root certificates stored in the Windows keystore.

1. If you have not already done so, include the sslN.jar archive in the archive parameter in the applet tag on the HTML page. This archive is not included in the complete JICAEng archive and you must include it before SSL or TLS encryption can be used.
2. Configure the Web server so that the HTML page specifying the applet can be delivered to the Web browser only through an SSL/TLS (https://) connection.

Caution: Security is seriously compromised if this step is omitted.

3. Enable SSL by adding the following parameter to the HTML page:

```
<param name="SSLEnable" value="on">
```

Configuring the Receiver for Use with Your Security Solution

You must perform further configuration if:

- You require the Citrix Receiver for Java to use TLS only.
- You are using a Secure Gateway server that is configured to run in relay mode.
- You are not using the default Cipher Suite. You may need to use the COM or GOV cipher suites to comply with your organization's security regulations. If you are not sure, contact your security administrator.
- Your organization has its own certification authority. You may need to import alternative root certificates to comply with your organization's security regulations. If you are not sure, contact your security administrator. Before importing a root certificate, it is important to verify the authenticity of the certificate. Your organization should have a procedure in place for users to check the root certificate as they import it.
- Your organization uses root certificates stored in the Microsoft Windows keystore. Where the user device is running Microsoft Windows, Microsoft Internet Explorer, and Java 1.6.16, the receiver is able to use root certificates stored in the Windows keystore (in addition to the root certificates in the Java keystore). Java must be configured accordingly.

To force TLS connections

To force receivers to connect only with TLS, you must specify TLS on the Secure Gateway server or SSL relay service.

1. Specify the following parameter in the HTML page:

```
<param name="SecureChannelProtocol" value="TLS">
```

To specify a Secure Gateway server that is configured to run in Relay mode

1. Add the following parameter to the HTML page:

```
<param name="SSLProxyHost" value="address:port">
```

where *address* is the fully qualified domain name of the Secure Gateway server and the same domain name specified in the server certificate. If the server port is not 443, specify the port.

To use a different Cipher Suite

1. Add the following parameter to the HTML page:

```
<param name="SSLCiphers" value="All|COM|GOV"
```

where:

All

- SSL_RSA_WITH_RC4_128_MD5
- SSL_RSA_WITH_RC4_128_SHA
- SSL_RSA_WITH_3DES_EDE_CBC_SHA

COM

- SSL_RSA_WITH_RC4_128_MD5
- SSL_RSA_WITH_RC4_128_SHA

GOV

SSL_RSA_WITH_3DES_EDE_CBC_SHA

Importing Root Certificates

In addition to the default root certificates provided by the JRE and the Windows keystore, you can import your own root certificates.

By default, the maximum key length is limited to 2048 bits. If you require support for key lengths up to 4096 bits, download the Java Cryptography Extension (JCE) Unlimited Strength Jurisdiction Policy File on each user device. The file can be downloaded from the relevant site.

To import root certificates with Java Keytool

You can import your own root certificates using the Java keytool utility. The root certificates you import are stored in the JRE keystore. Use the Java keytool utility to import certificates for each user device. It is not possible to import certificates using the Java Control Panel.

1. Use the following sample at a command prompt to import a root certificate:

```
keytool -import -trustcacerts -alias myrootcert  
-file c:\bin\rootcert.cer -keystore  
c:\Program Files\Java\jre6\lib\security\cacerts
```

where C:\Program Files\Java\jre6\ is the JRE directory.

The *keystore* parameter is mandatory. The default password for the Java keystore is *changeit*.

2. Use the following command to change the password:

```
keytool -storepasswd -keystore c:\Program Files\Java\jre6\lib\security\cacerts
```

where 'c:\Program Files\Java\jre6\' is the JRE directory.

To use root certificates in the Windows Keystore

To allow the receiver to use root certificates in the Windows keystore, you must configure Java.

To use root certificates stored in the Windows keystore, the user device must be running Microsoft Windows, Microsoft Internet Explorer, and Java 1.6.16. The receiver uses these root certificates in addition to root certificates in the Java keystore.

1. From the Java Control Panel, select the **Advanced** tab. Within the **Security** settings, ensure **Use certificates and keys in browser keystore** is selected.

2. To add your own root certificates to the Windows keystore, double-click the required certificate file and follow the certificate installation instructions.

Note: Root certificates in the Windows keystore are available for use by all applications, not just the receiver. If this is not acceptable, disable the **Use certificates and keys in browser keystore** security option. This ensures the receiver uses root certificates in the Java keystore only.

Certificate Revocation List Checking

When connecting to a XenApp server using SSL or TLS, with certificate revocation list checking enabled, Citrix Receiver for Java checks whether or not the server's certificate is revoked.

You can enable several levels of certificate revocation list checking using the "SSLCertificateRevocationCheckPolicy" parameter values:

- **NoCheck** - No certificate revocation checking is performed.
- **CheckWithNoNetworkAccess** - The local CRL store is checked (default option).
- **FullAccessCheck** - The local CRL store and any CRLs available over a network are checked.
- **FullAccessCheckAndCRLRequired** - The local CRL store and any CRLs available over a network are checked and verified. The connection fails if a CRL cannot be found.

The location of the local CRL store is:

- **Microsoft Windows:** %USERPROFILE%\Citrix\crl
- **UNIX:** \$HOME/.Citrix/crl

Certificate Chains

The Sun Java virtual machine provides two certificate validation engines: SunX509 and SunPKIX. You select the required validation engine in the `java.security` file (for example, `C:\Program Files\Java\Jre6\Lib\Security\Java.security`) using the “`ssl.TrustManagerFactory.algorithm`” parameter:

```
ssl.TrustManagerFactory.algorithm=[SunX509|PKIX]
```

where `C:\Program Files\Java\Jre6` is the JRE directory

The validation engine selection determines the certificate chain length:

- SunX509 allows certificate chains of up to three certificates
- PKIX allows certificate chains of up to five certificates

PKIX is often the choice of validation engine within government deployments. However, the choice of certificate validation engine is dependent on your organization’s security policy.

Connecting to a Server Across a Firewall

Network firewalls can allow or block packets based on the destination address and port. If you are using Citrix Receiver for Java through a network firewall that employs IP address translation, specify the following parameters:

- **UseAlternateAddress:** Use an alternate address across a firewall (specified by the parameter HTTPBrowserAddress). The values are 0 (default; actual address is used) and 1 (alternate address is used). If this parameter is set to 1, the parameter HTTPBrowserAddress must also be specified. Setting this parameter to 0 is the same as not using the parameter.

You can also enable alternate addressing using the **ICA Settings** dialog box.

- **HTTPBrowserAddress:** The external Internet address of a server.

Note: All servers in the farm must be configured with their alternate (external) address.

For example, to connect to a server across a firewall in applet mode and use an alternate address for the server Fountain, create an HTML page like the following:

```
<html>
  <body>
    <applet code="com.citrix.JICA"
      archive="JICAEngN.jar"
      width="640" height="480">
      <param name="Address" value="Fountain">
      <param name="HTTPBrowserAddress" value="177.17.1.7">
      <param name="user.wfclient.UseAlternateAddress"
        value="1">
    </applet>
  </body>
</html>
```

To specify ICA encryption

The default level for ICA encryption is Basic. To enable encryption levels higher than Basic, the following conditions must be present:

- The server is configured to allow the selected encryption level or higher. To enable encryption levels higher than Basic, the server must support RC5 encryption.
- If you are using the core archive, include the cryptojN and JICA-sicaN archives in the archive attributes on the HTML page. If you are using a complete JICAEngN archive, include the cryptojN archive.

1. Use the following parameter on an HTML page:

```
<param name="EncryptionLevel" value="0|1|2|5">
```

The number you type corresponds to the encryption level required as follows:

Level	Description
0	No encryption (needs server setup; default is Basic).
1	Basic encryption. This is the default.
2	RC5 128-bit encryption during authentication. After the logon process is successfully completed, the encryption level changes to Basic.
5	RC5 128-bit. This is intended for users who are dealing with sensitive data and need a high level of privacy and integrity.

To create a connection to a server called CitrixServer using 128-bit ICA encryption, create an HTML page like the following example:

```
<html>  
  <body>  
    <applet code="com.citrix.JICA"  
      archive="JICA-coreN.jar,cryptojN.jar,JICA-sicaN.jar"  
      width="640" height="480">  
      <param name="Address" value="CitrixServer">  
      <param name="EncryptionLevel" value="5">  
    </applet>  
  </body>  
</html>
```

Configuring Kerberos Authentication

Citrix XenApp 6, XenApp 5, and Citrix Presentation Server 4.5 extend the use of Kerberos. Users can log on to the user device with any authentication method, for example, using a smart card, and access published resources without further authentication. The user's password is not transmitted to XenApp—instead, authentication tokens are exchanged. This authentication exchange is performed within an ICA virtual channel and does not require any additional protocols or ports.

Kerberos logon is not available in the following circumstances:

- Connections for which you select any of the following options in Terminal Services Configuration:
 - On the **General** tab, the **Use standard Windows authentication** option
 - On the **Logon Settings** tab, the **Always use the following logon information** option or the **Always prompt for password** option
- Connections you route through the Secure Gateway for XenApp
- The XenApp server requires smart card logon
- The authenticated user account requires a smart card for interactive logon

The default security settings have changed on a number of releases of the Microsoft Windows operating system, including Windows Server 2003 and Windows XP with Service Pack 2. To ensure Kerberos functions on these platforms, set the following registry setting on each client device:

```
AllowTGTSessionKey = 0x01 (DWORD)
```

The location of the registry setting differs depending on the operating system. On Windows XP with Service Pack 2, the setting is stored in:

```
HKLM\SYSTEM\CurrentControlSet\Control\Lsa\Kerberos
```

To configure the receiver for Kerberos logon

Citrix Receiver for Java, by default, is not configured to use Kerberos authentication when logging on to the server. When the receiver is configured, the user logs on using Kerberos authentication only. If Kerberos logon fails for any reason, the user is prompted for credentials. Kerberos can fail due to a missing operating system requirement, such as the requirement that the server be trusted for delegation.

1. Use the following parameter to enable Kerberos logon:

```
<param name="UseLocalUserAndPassword" value="on">
```

Configuring UNIX Kerberos Authentication

It is possible to configure Kerberos-enabled UNIX and Microsoft Windows domains to allow users working on UNIX user devices to access Citrix XenApp using their UNIX Kerberos credentials.

The receiver must be configured for Kerberos as detailed in "To configure the receiver for Kerberos logon". There are no other special requirements for the receiver; however, there are some prerequisites:

- Your UNIX and Microsoft Windows domains must be configured to allow Kerberos authentication across the domains. The requirements and process differs depending on your UNIX Kerberos installation. See your UNIX Kerberos documentation and your Windows Kerberos documentation for information.
- Within your UNIX Kerberos installation, you may need to specify the relevant Windows domains (the domains in which the XenApp servers are located).

Additional information on this topic is available at <http://www.microsoft.com>.

Locating Receiver Configuration and Device Files

Citrix Receiver for Java configuration is stored in three places:

- The HTML page, stored on a Web server
- The ICA file, from a server running the Web Interface or from a standard Web server
- The Appsrv.ini file, stored on the user device

Most parameters specified on the HTML page take precedence over those specified in the ICA file. Similarly, parameters specified in the ICA file take precedence over those in the appsrv.ini file. Note that some parameters can be specified only in the .ini file.

The location of the Appsrv.ini configuration file depends on the user device operating system. The locations for some common operating system are:

Windows:

%USERPROFILE%\Citrix

UNIX and Linux:

\$HOME/.citrix

Mac OS X:

<User's home directory>/ .citrix

Files Stored on the User Device

File	Description
Appsrv.ini	Stores settings from the Settings user interface, except receiver name.
Wfcname.ini	Stores the receiver name. The file is stored in the same directory as Appsrv.ini.
*.jfn	If local text echo is enabled, glyphs are cached in files with the .jfn suffix. These files are stored in the same directory as Appsrv.ini.
Graphical objects (Citrix proprietary format)	If bitmap caching is enabled, cached graphics are stored in the Cache subdirectory (which appears in the directory in which the Appsrv.ini file is stored).

*.crl	<p>If certificate revocation checking (CRL) is enabled, CRL files are stored in Crl or Crl/Cache.</p> <p>Users can place CRLs in the Crl directory. The receiver caches CRLs in the Crl/Cache directory.</p> <p>CRLs are not deleted from the Crl directory (whereas CRLs may be deleted from the Crl/Cache directory when they expire).</p> <p>The CRL directories appear in the directory in which the file Appsrv.ini is stored.</p>
CTX.DAT	<p>The file contains data that is used to identify the user device for Terminal Services licensing purposes. The receiver attempts to create the file in the following locations, in the following order:</p> <ul style="list-style-type: none">• UNIX platforms only: /usr/local• Windows platforms only: C:\ through Z:\• All platforms: directory specified by the Java system property <java.home>• All platforms: directory specified by the Java system property <user.home> <p>If the receiver is unable to create the file, the network IP address is used to identify the user device. This may lead to the receiver consuming multiple client access licenses in a Dynamic Host Configuration Protocol environment.</p>

Improving Performance of the Receiver for Java

Reducing System Overhead With Session Sharing

If you are not using seamless windows, consider moving to this mode of working to gain the performance benefits of session sharing. These include a reduction in system overhead for both user device and server and quicker application launching.

Compressing Data to Reduce the Amount of Data Transferred Over the Network

Data compression reduces the amount of data that needs to be transferred over the network. However, additional processor resources are required to compress and decompress the data. If your connection is bandwidth-limited, enabling data compression improves performance.

You can specify two levels of data compression, standard and maximum. Maximum data compression uses more processor power and memory and may reduce performance on slow devices. Data compression is enabled by default.

To enable maximum data compression, specify the following parameters on the HTML page:

```
<param name="Compress" value="on">  
<param name="MaximumCompression" value="on">
```

To disable data compression specify the following parameter on the HTML page:

```
<param name="Compress" value="off">
```

Caching Bitmap Images to Increase Their Rendering Speed

Bitmap caching stores commonly used images on a local disk. If the connection is bandwidth-limited, using bitmap caching increases performance. If the client is on a high-speed LAN, you do not need bitmap caching.

You can configure bitmap caching using parameters on the HTML page or the user can do it through the **ICA Settings** dialog box.

To enable bitmap caching for a connection specify the following parameter on the HTML page:

```
<param name="PersistentCacheEnabled" value="on">
```

The bitmap cache directory is stored in the directory specified by the standard Java system property `user.home`. The location of the `user.home` directory depends on the Java environment or Web browser you are using. If necessary, use the **ICA Settings** dialog box to change the bitmap cache directory.

Queuing Mouse Movements to Reduce Mouse Events Sent to the Server

When queuing is enabled, the client sends mouse movement updates less frequently to the server. This prevents the connection from becoming overburdened with excessive mouse events, which would degrade performance. Disabling queuing makes the ICA session more responsive to mouse movements. By default, mouse queuing is disabled.

To change the update period for mouse movement queuing, specify the following parameter on the HTML page:

```
<param name="MouseTimer" value="period">
```

where *period* is the update period you are using, in milliseconds. To disable mouse movement queuing, set the period to zero.

Providing Instant Onscreen Feedback to User Input by Using SpeedScreen Latency Reduction

SpeedScreen latency reduction improves performance over high latency connections by providing instant feedback to the user in response to typed data or mouse clicks.

SpeedScreen latency reduction is available only when it is enabled on the server to which the user device connects.

SpeedScreen latency reduction is not available on the Japanese receiver

Improving Performance over a Low-Bandwidth Connection

If you are using a low-bandwidth connection, such as a modem or cellular telephone, for your sessions, you can make a number of changes to your Citrix Receiver for Java configuration and the way you use the receiver that will improve performance:

- **Reduce the receiver download size.** If you do not require the entire functionality of the receiver, specify only the archives necessary to provide the functions you require. Reducing the size of the applet can greatly reduce the download time.
- **Change the receiver configuration.** On devices with limited processing power, or where limited bandwidth is available, there is a trade-off between performance and functionality. The receiver provides both the user and administrator with the ability to choose an acceptable mixture of rich functionality and interactive performance. Making one or more of the following changes can reduce the bandwidth that the connection requires and improve performance:
 - **Enable maximum data compression.** Compression reduces the size of the data that is transferred over the connection.
 - **Enable the bitmap cache.** Bitmap caching stores commonly used images locally on the user device so that they do not have to be transferred over the connection every time they are needed.
 - **Queue mouse movements.** When queuing is enabled, the receiver sends mouse updates to the server less frequently. Increasing the queuing period may improve performance on a low-bandwidth connection.
 - **Enable SpeedScreen latency reduction.** SpeedScreen latency reduction improves performance over high latency connections by providing instant feedback to the user in response to typed data or mouse clicks.
 - **Reduce the window size.** Change the window size to the minimum size users can comfortably use.
 - **Reduce the number of colors.** Reduce the number of colors to 256.
 - **Disable receiver audio mapping.** If users do not need sound, disable receiver audio mapping or remove the JICA-audio archive.
 - **Disable clipboard mapping.** If users do not need to copy and paste text, do not include the JICA-clipboard archive.
 - **Disable client drive mapping.** If users do not need to map drives, do not include the JICA-cdm archive.
 - **Disable printing.** If users do not need to map printers, do not include the JICA-printer archive.

- **Disable server browsing.** If providing connections to desktops only (not published applications), do not include the JICA-browse archive.
- **Change the way you use the receiver.** Users on a low-bandwidth connection should consider the following to preserve performance:
 - **Avoid accessing large files using client drive mapping.** When you access a large file with client drive mapping, the file is transferred over the connection. On slow connections, this may take a long time.
 - **Avoid printing large documents on local client printers.** When you print a document on a locally mapped printer, the print file is transferred over the connection. On slow connections, this may take a long time.
 - **Avoid playing multimedia content.** Playing multimedia content uses a lot of bandwidth and can cause reduced performance.
- **Use the latest receiver and server software.** Citrix is continually enhancing and improving performance with each release, and many performance features require the latest receiver and server software in order to function.

Limitations of the Receiver for Java

User Device Drive Mapping

A remote application generates an error message because it cannot lock a file.

Due to Java limitations, Java programs cannot lock files. This means that files cannot be locked on mapped local drives.

To avoid generating error messages, disable the Safelock option on the HTML page:

```
<param name="Safelock" value="off">
```

When Safelock is disabled, if a remote application attempts to lock a file on a mapped drive, the receiver will report success. However, this does not mean that the file is locked; you must take precautions to ensure that another application does not write to or delete the same file, because this could result in data corruption.

Mouse Pointer Support

In shadowed sessions, the mouse pointer does not move when shadowing users move their mouse pointer.

Seamless Windows

On some platforms, the *outline* drag-box that appears when you move or resize seamless windows can cause unattractive repaint effects. If you experience this, you can either specify a solid drag-box type or eliminate the drag-box entirely by setting the parameter `TWIDragBoxType` to `solid` or `none` respectively.

Server Names with non-ASCII Characters

For user device operating systems to contact servers, the host name and domain name must be compliant with the Domain Naming System (DNS). That is, the names must contain only upper- and lower-case ASCII a to z, digits 0 to 9, and dash (-). This may not be necessary when user device operating systems and the DNS server support multinational characters.

Published application names can comprise any characters because these are always resolved by the ICA browser. Note that any ICA browser addresses have the same DNS restrictions as the server names described above.

On some systems, you may not be able to connect to a server if its name does not conform to this requirement (that is, a server with a Japanese name or a name containing other non-ASCII characters).

To avoid this, do one of the following:

- Conform to the DNS requirement and use only ASCII characters in server names.
- Specify ICA browser addresses as IP addresses and do not enable DNS resolution for the server. If you do both of these things, the servers can have names that do not comply with the DNS requirement; however, SSL does not work in this scenario because DNS names are required for certificate validation. In addition, the Web Interface does not work because DNS is used to resolve the hostname part of the Web Interface URL.

Universal Print Driver and PCL4

- Horizontal lines in text and images sometimes appear jagged in landscape mode
- Print output near the page edge is sometimes clipped when you are using small page margins

To avoid these problems, use the appropriate native printer driver instead of the UPD. Configure the driver using the **Settings** dialog box and ensure that it is available on the server.

Working with Linux and Solaris

Loss of Keyboard Focus

On Linux and Solaris platforms, the applet in embedded or non-seamless mode can lose keyboard focus after opening a receiver dialog box. The keyboard focus is successfully passed to the dialog box when the dialog box is opened, but it is lost when the dialog box is closed.

For Solaris, the workaround is to give keyboard focus to another application's window, then give it back to the browser window containing the embedded receiver applet. For Linux, click in the applet to restore keyboard focus.

Clipboard Support on X11

- Clipboard support on the Citrix Receiver for Java works only with applications that use the X11 CLIPBOARD selection. Specifically, Motif and Gnome applications are fine, but KDE applications do not work. Xterm can be configured with X11 resources to use the CLIPBOARD selection. For example:

```
XTerm*VT100.Translations:          #override \n\  
-Ctrl -Meta <Btn2Up>:\n  
insert-selection(PRIMARY,CLIPBOARD,CUT_BUFFER0)\n\  
<BtnUp>: select-end(PRIMARY,CLIPBOARD,CUT_BUFFER0)\n
```

GNU Emacs can also be configured to use CLIPBOARD with the following Emacs lisp:

```
(setq x-select-enable-clipboard t)
```

- The xclipboard utility (present on most X11 systems) may be of use in transferring data between the PRIMARY and CLIPBOARD selections.

Working with the Mac OS X

- To right-click when connected to a Citrix XenApp computer with a Macintosh, press the command key and click the mouse button.
- Characters generated using the Option keys on a Macintosh may not be supported by the current Windows font in your session. If the character produced is not the expected character, choose a Windows font in the session that supports the character. After producing the desired character, you can return to the usual font.
- Citrix Receiver for Java cannot load when the Java archive files are hosted on a Web server that requires cookies or authentication before serving the files. Ensure that the Web server does not require authentication to serve these files.

This issue also affects the HTML help and .ica files.

In particular, .asp or .jsp applications that manage session state using cookies are affected.

- Arbitrary mouse pointers are not supported on Mac OS X.

Working with Windows Internet Explorer

Displaying Dead Key Characters

To display dead key characters, press a dead key, then press the SPACEBAR twice.

Enabling Java Environments when Logged on as Administrator

For Windows Server 2008 R2, the default security settings when you log on with administrator privileges are:

- Internet = Medium-high
- Local Intranet = Medium-low
- Trusted Sites = Medium

If you log on as an administrator and use Citrix Receiver for Java over the Internet, enable Java environments for the High security level through Internet Explorer's Internet Options.

- Follow the instructions given in Microsoft Knowledge Base article 182569.
- Accept the Internet site that provides the Java applet as a trusted site. The default security level for a trusted site is Medium, therefore the Java environment is enabled, and you can use the client.

Using the Receiver for Java on Japanese Operation Systems

Typing Japanese Characters in Shadowing Sessions

If you shadow another session, use the server Input Method Editor (IME). By default, the server-side IME is used, but if you have been using the IME on the user device, change your keyboard layout setting.

From the **ICA Settings** dialog box, choose the **General** tab, followed by either (**Server Default**) or **Japanese (server IME only)** from the **Keyboard Layout** options.

Alternatively, you can choose **Japanese (client and server IME)** and use the server IME during shadowing.

Typing the Long Vowel Sound Symbol (—) in Kana Input Mode

When using the server IME to type Japanese characters in Kana input mode, press **SHIFT+—** to enter the long vowel symbol. This is not necessary when using the client IME.

Typing Japanese Characters in Applications Using the IME on the User Device

If you use the IME on the user device, displayed characters may be corrupted when you are using certain applications. If this happens, use the server IME instead.

Web Interface on Windows Unicode Settings

If you are using the Web Interface for XenApp, installed on a Microsoft Windows server, to deploy the Citrix Receiver for Java, Citrix recommends that you configure the Web Interface to deploy Version 8 or later clients. This ensures all ICA files are encoded in Unicode.

Configure this setting using the Delivery Services Console. When specifying the launch client settings, set the client version support option to version 8 or later clients.

If this option is not selected, ICA files are encoded using Microsoft Windows Codepage 932. Although this is acceptable in many circumstances, users will not be able to launch published applications if the application name includes certain characters, such as a long tilde.

Hotkey Support for Japanese Keyboards

On certain hardware platforms, some Java environments may have problems with the special Japanese modifier keys, such as Hankaku, Zenkaku, and Hiragana, which are used to control the IME on the server.

If you experience this problem, first ensure that you have the Java SE Runtime Environment (JRE) 6 Update 18 environment for your platform. If the problem persists, you can interact with the IME by clicking the IME buttons using your mouse.

Alternatively, define hotkeys to simulate the effect of the IME keys. For example, you can define **F1** as the Katakana key. This technique for mapping hotkeys is similar to that used for defining special key combinations for the client, such as using **CTRL+F1** to send the key combination **CTRL+ALT+DEL**.

Define Japanese hotkeys in the same way as English hotkeys: either in the `<applet>` tag or by using the **ICA Settings** dialog box, as described in [Specifying Hotkey Functions](#).

The full set of possible Japanese hotkeys is:

HotkeyMuHenkanChar
HotkeyMuHenkanShift

HotkeyPrevKouhoChar
HotkeyPrevKouhoShift

HotkeyKatakanaChar
HotkeyKatakanaShift

HotkeyHankakuChar
HotkeyHankakuShift

HotkeyKanjiBangoChar
HotkeyKanjiBangoShift

HotkeyNextKouhoChar
HotkeyNextKouhoShift

HotkeyAllKouhoChar
HotkeyAllKouhoShift

HotkeyHiraganaChar
HotkeyHiraganaShift

HotkeyRomajiChar
HotkeyRomajiShift

HotkeyEisuChar
HotkeyEisuShift

Using Client-side IME Input Mode on Mac OS X

Using ATOK

When using the client on Japanese Mac OS X with the ATOK IME, use ATOK17. Citrix Receiver for Java is not supported with ATOK16. Alternatively, use the default Kotoeri IME.

Displaying the First Character Typed

When using an IME on a user device running Mac OS X, if the first character you type is a full width Roman (a-z) character, it is not displayed.

To display the first character, either:

- Use the server-side IME to input full width Roman characters.
- Type one or more kana characters before typing a full width Roman character.

Changing the Input Mode

Key combinations using the Apple (**Alt**) key can switch focus to the application menu bar, which results in the first character you type not being recognized.

When using an IME on a user device running Mac OS X, use the kana and eisu keys to switch the IME input mode.

Typing Characters After Reconnecting Using the IME on the User Device

If you reconnect to a session from a different browser or with a different window size setting from the original session, you may see a dialog box warning you that the video mode for the existing session cannot change. You cannot input characters using the IME on the user device until you close the dialog box by clicking **OK**.

Sometimes this dialog box is displayed behind the application window. If you cannot type characters using the IME on the user device after reconnecting, even if you do not see a dialog box, try minimizing the application window in the browser window to see whether the warning dialog box appears. Close the dialog box by clicking **OK**, then restore the application window.

Parameters for the Receiver for Java

The following tables list the parameters most frequently specified to provide additional features and customization. The **Address** parameter is the only required parameter.

You specify most of the parameters on the HTML page; however, you specify the receiver drive mapping parameters listed in this section in the appsrv.ini file on the user device.

Parameter	Description
Address	The address of the server or the name of the published application. If a published application is entered as an address value, the InitialProgram parameter must also be specified.
CGP Address	The address of the session reliability server: "hostname:port". Type an asterisk (*) to use the Address parameter value as the session reliability server.
Clientname	The receiver name. Use in the form client.wfclient.Clientname. Use with the parameter client.wfclient.UseHostname=off.
CREnabled	Specifies whether or not content redirection is enabled. Values are yes or no. The default value is yes.
Domain	The name of the domain for the user name.
HTTPBrowserAddress HTTPBrowserAddress2 to 15	<p>The address of a browser server. This parameter is used when TCP/IP+HTTP or SSL/TLS+HTTPS browsing has been specified. This parameter is also used to designate groups of primary and backup servers.</p> <p>Note that when the XML Service on the server is not configured to use the default port 80, you must append <i><port number></i> to this parameter, substituting <i><port number></i> with the port number your server's XML Service is configured to use.</p> <p>For HTTPBrowserAddress the default is ica. There is no default for HTTPBrowserAddress 2 to 15.</p>
Icafile	An ICA file for the receiver to use. The value entered must be a valid URL. There is no default.
ICAPortNumber	The default ICA port number is 1494. You can specify a different port number using this parameter or by appending the port number to the address value; for example, CitrixServer:1495.
InitialProgram	The name of the initial program to run after connecting to the server. If you are connecting to a published application, add a # symbol before the program name.

Parameters for the Receiver for Java

Language	Causes the receiver's user interface components to appear in a language other than the language of the user device.
Param	Passes a parameter such as a file name to a published application.
Password	The user's password. The Password parameter cannot be used to specify an encrypted password. To specify an encrypted password, use an ICA file or .ini file that contains an encrypted password.
SupportTSEquivalencyOnWinXP	Specifies whether or not Microsoft Terminal Services Client Access License equivalency is used on Microsoft Windows XP user devices. Values are on or off. The default value is off.
TWIDisableSessionSharing	Specifies whether or not session sharing is disabled. Used in conjunction with the Connection Center. The default value is no.
TWIMode	Enables seamless windows. If you are using seamless windows, set this parameter to on; otherwise, set it to off.
UseHostname	Specifies using the hostname as the receiver name. Use in the form client.wfclient.UseHostname.
Username	The user name to use during logon.
WorkDirectory	The path of the working directory where the initial program is run after the user connects to the server.

Security Integration Parameters

Parameter	Description
EncryptionLevel	<p>The level of ICA encryption to use for an ICA connection. Values are as follows:</p> <p>0 = No encryption, 1 = basic encryption, 2 = RC5 128-bit encryption during authentication only, 5 = RC5 128-bit</p> <p>The default value is 1.</p>
PermitCGP	<p>Specifies whether or not session reliability is allowed (parameter set on the user device). Values are yes or no. The default value is yes.</p>
PermitVirtualChannelSDK	<p>Specifies whether or not the SDK virtual channel is allowed (parameter set on the user device). Values are yes or no. The default value is no.</p>
ProxyAutoConfigURL	<p>The location of a Proxy Auto Configuration (PAC) file for automatic proxy configuration. There is no default value.</p> <p>(This parameter is meaningful only if you specify ProxyType.)</p>
ProxyDebug	<p>Specifies whether or not to enable proxy debugging in the Java console for troubleshooting purposes. Values are on or off. The default value is off.</p> <p>(This parameter is meaningful only if you specify ProxyType.)</p>
ProxyExcludeList	<p>A semicolon- or comma-separated list of addresses of servers that the receiver must connect to directly—not through the proxy server. There is no default value.</p> <p>(This parameter is meaningful only if you specify ProxyType.)</p>
ProxyHost	<p>The location and port of the proxy server. There is no default value.</p> <p>(This parameter is meaningful only if you specify ProxyType.)</p>

ProxyType	<p>The type of proxy server. Values are:</p> <p>none = no proxy</p> <p>auto = use the Web browser's settings</p> <p>socks = use SOCKS and automatically detect the version socks4 = use SOCKS Version 4</p> <p>socksv5 = use SOCKS Version 5</p> <p>secure = use Secure proxy</p> <p>script = use a PAC file (specified by ProxyAutoConfigURL)</p> <p>There is no default value.</p>
ProxyUsername ProxyPassword	<p>Proxy server logon credentials. There is no default value.</p> <p>(These parameters is meaningful only if you specify ProxyType.)</p>
SecureChannelProtocol	<p>Specifies the SSL/TLS protocol version. Values are SSL, TLS, or detect. If you specify detect, the receiver connects using the protocol requested by the server. The default value is detect.</p>
SSLCertificateRevocationCheckPolicy	<p>Specifies whether or not to use Certificate Revocation Checking. Values are NoCheck, CheckWithNoNetworkAccess, FullAccessCheck, and FullAccessCheckAndCRLRequired.</p> <p>The default value is CheckWithNoNetworkAccess.</p>
SSLCiphers	<p>An alternative cipher suite. Values are Gov, Com, or All. The default value is All.</p>
SSEnable	<p>Enables SSL and TLS encryption protocols. Used with the BrowserProtocol parameter. Values are on or off. The default value is off.</p>
SSLProxyHost	<p>A Secure Gateway (relay mode) address. There is no default value.</p>
UseAlternateAddress	<p>Specifies whether or not to use an alternate server address across a firewall. Used in the form user.wfclient.UseAlternateAddress.</p> <p>Values are 0 (actual address is used) or 1 (alternate address is used). The default value is 0.</p>
UseLocalUserAndPassword	<p>Specifies whether or not to configure the receiver for Kerberos support. Values are yes or no. The default value is no.</p>

User Interface Parameters

Parameter	Description
Border	Turns the border around the session in the browser window on or off. Values for this parameter are on or off. The default value is off.
BorderWidth	The border width in pixels. The default value is 6.
DesiredColor	The color depth of the session windows. The values are 2 (256 colors), 4 (thousands of colors), and 8 (millions of colors). The default value is 256 colors. 16 color mode is not supported but the receiver can connect to applications published in 16 color mode, in which case 256 colors are used.
DesiredHRes	The height of the session window, if you want the session size to be different from the applet size. If this parameter is not specified, the Height parameter is used and the session height is therefore the same as the applet height. There is no default.
DesiredVRes	The width of the session window, if you want the session size to be different from the applet size. If this parameter is not specified, the Width parameter is used and the session width is therefore the same as the applet width. There is no default.
End	Controls the receiver's behavior when you terminate a session. The values are manual (default), auto, terminate, and URL.
Height	The height of the session window. This parameter is specified as an attribute in the <applet> tag.
HotkeynShift HotkeynChar	Sets hotkeys that can be used to control various receiver functions. Use in the form user.wfclient.HotkeynShift or user.wfclient.HotkeynChar where <i>n</i> is the number of the hotkey. <i>n</i> can be 2, 3, 4, 5, 6, 7, 8, 9, 10, or 11. For information about how to set hotkeys, see Specifying Hotkey Functions .
KeyboardLayout and KeyboardType	The type of keyboard. Use in the form user.wfclient.KeyboardType and user.wfclient.KeyboardLayout.
ShowSettingsButton	Specifies whether or not to show the Settings button. You must include the complete JICAEng archive or the JICA-config archive to display the Settings button. Values for this parameter are yes or no. The default value is yes.

User Interface Parameters

ShowStatusBar	Specifies whether or not to show the status bar. You must include the complete JICAEng archive or the JICA-config archive to display the status bar. Values for this parameter are yes or no. The default value is yes.
Start	Controls the receiver's behavior when you start a session. The values are manual and auto. The default value is manual.
Width	The width of the session window. This parameter is specified as an attribute in the <applet> tag.

Client Audio Mapping Parameters

Parameter	Description
ClientAudio	Enables receiver audio. The values are on and off. The default is off.

Receiver Printer Mapping Parameters

Parameter	Description
Comment	Sets a default printer. Must be specified as <code>user.printername.Comment</code> , where <i>printername</i> is the name allocated with the parameter <code>LocalClientPrinters</code> .
Driver	The printer driver. Use in the form <code>user.printername.Driver</code> , where <i>printername</i> is the name allocated with the parameter <code>LocalClientPrinters</code> .
LocalClientPrinters	Used for passing information about receiver printers to the server. Must be specified as <code><param name="user.localclientprinters" value="printername"></code> . To specify more than one printer, separate the printer names with commas.
Port	The printer port. Use in the form <code>user.printername.Port</code> , where <i>printername</i> is the name allocated with the parameter <code>LocalClientPrinters</code> .

Client Drive Mapping Parameters

Although the user specifies most client drive mapping parameters using the **ICA Settings** dialog box, there are three parameters that you can specify only in the `appsrv.ini` file on the user device:

Parameter	Description
<code>DriveRemovable<x></code>	Specifies whether or not drive x is removable, such as a DVD drive. Values for this parameter are yes or no. The default is no.
<code>DriveMappingHomeDrive</code>	Specifies the drive letter to use for the home drive. The value must be a single letter. The default is H.
<code>DriveMappingAutoDetectHome</code>	Specifies whether or not to auto-detect the user's home drive. Values for this parameter are yes or no. The default is yes.

Performance Tuning Parameters

Parameter	Description
Compress	Sets data compression. The values are on to enable data compression and off to disable it. The default value is on.
MaximumCompression	Sets high level data compression. The values are on to enable greater data compression and off to select normal data compression. Requires the Compress parameter to be enabled. The default value is off.
MouseTimer	The time (in milliseconds) between the mouse movement updates that are sent to the server. Set to 0 to disable queuing. The default value is 0.
PersistentCacheEnabled	Enables or disables bitmap caching. Must be specified as "user.wfclient.PersistentCacheEnabled". Values are on or off. The default value is off.
PersistentCacheMinBitmap	The size of the smallest bitmap to cache, in KB. The default value is 8.
PersistentCacheSize	The size of the bitmap cache in MB. The default value is 10.
ZLKeyboardMode	SpeedScreen latency reduction mode. The values are 0 (off), 1 (on), or 2 (auto). The default value is 0.
ZLMouseMode	SpeedScreen latency reduction mode. The values are 0 (off), 1 (on), or 2 (auto). The default value is 2.