


# Configuring Zoho


1. Login to Zoho as an Admin user.



2. To get SAML Authentication page, you need to sign into **Zoho mail** and verify your account then login into **Zoho Account** again.
3. Zoho Accounts window will appear, click on **Preferences**.



4. Settings window will appear, click on **SAML Authentication**.



5. SAML Authentication window will appears, click on **Setup Now**.



6. Complete all the fields with appropriates values and click on **get key from file** and upload your **IdP certificate**.

## SAML Authentication

SAML is an XML-based framework for exchanging user authentication, entitlement, and attribute information between different systems.

Login URL [https://ug1.<customer\\_domain>.com/saml/login](https://ug1.<customer_domain>.com/saml/login)

Logout URL [https://ug1.<customer\\_domain>.com/cgi/logout](https://ug1.<customer_domain>.com/cgi/logout)

Do you need Logout Response?

Change Password URL [https://ug1.<customer\\_domain>.com/cgi/logout](https://ug1.<customer_domain>.com/cgi/logout)

PublicKey



[Get key from file](#)  4

Algorithm RSA

Just In Time Provisioning


Zoho Service Accounts

 **Add** **Cancel**

7. Update all the fields in SAML authentication page and click on **Add**.

Field Name	Values
Login URL	<a href="https://ug1.&lt;customer_domain&gt;.com/saml/login">https://ug1.&lt;customer_domain&gt;.com/saml/login</a>
Logout URL	<a href="https://ug1.&lt;customer_domain&gt;.com/cgi/logout">https://ug1.&lt;customer_domain&gt;.com/cgi/logout</a>
Change password URL	<a href="https://ug1.&lt;customer_domain&gt;.com/cgi/logout">https://ug1.&lt;customer_domain&gt;.com/cgi/logout</a>
Public Key	Update IdP Certificate

8. In place of <customer\_domain>, enter your customer domain name (See **Introduction** to know more about the <customer\_domain> values).
9. SAML Authentication window will appear, click on **download metadata**.



10. Copy **customer id** from your metadata.

```
<md:AssertionConsumerService  
  Location="https://accounts.zoho.com/samlresponse/00000000000000000000000000000000"  
  Binding="urn:oasis:names:tc:SAML:2.0:bindings:HTTP-POST"  
  isDefault="true" index="0"/>
```

Customer id



Default authentication type for embedded views

- Allow users to choose their authentication type
- Tableau
- .com (SAML)