

Device property names and values

Property name in Manage > Devices page	Name and values for device provisioning file	Values (meaning)	Value type
AIK Present?	WINDOWS_HAS_AIK_PRESENT		String
Account Suspended?	GOOGLE_AW_DIRECTORY_SUSPENDED		String
Activation lock bypass code	ACTIVATION_LOCK_BYPASS_CODE		String
Activation lock enabled	ACTIVATION_LOCK_ENABLED	1 (Yes) 0 (No)	Boolean
Active iTunes account	ACTIVE_ITUNES	1 (Yes) 0 (No)	Boolean
ActiveSync ID	EXCHANGE_ACTIVASYNC_ID		String
ActiveSync device known by MSP	AS_DEVICE_KNOWN_BY_ZMSP	1 (True) 0 (False)	Boolean
Administrator disabled	ADMIN_DISABLED	1 (Yes) 0 (No)	Boolean
Amazon MDM API available	AMAZON_MDM	1 (True), 0 (False)	Boolean
Android for Work Device ID	GOOGLE_AW_DEVICE_ID		String
Android for Work Enabled Device?	GOOGLE_AW_ENABLED_DEVICE		String

Property name in Manage > Devices page	Name and values for device provisioning file	Values (meaning)	Value type
Android for Work Install Type	GOOGLE_AW_INSTALL_TYPE	DeviceAdministrator (Device Owner) AvengerManagedProfile (Work Managed Device) ManagedProfile (Work Profile)	String
Antispyware Signature Status (Windows 10)	ANTI_SPYWARE_SIGNATURE_STATUS		Boolean
Antispyware Status (Windows 10)	ANTI_SPYWARE_STATUS		Boolean
Antivirus Signature Status (Windows 10)	ANTI_VIRUS_SIGNATURE_STATUS	Not recent version Most recent version N/A	String
Antivirus Status (Windows 10)	ANTI_VIRUS_STATUS	ON and monitoring Disabled OFF or not monitoring Temporarily not monitoring N/A	String
Asset tag	ASSET_TAG		String
Autoupdate Status	AUTOUPDATE_STATUS		String
Available RAM	MEMORY_AVAILABLE		Integer
Available storage space	TOTAL_DISK_SPACE		Integer
BIOS Info	BIOS_INFO		String

Property name in Manage > Devices page	Name and values for device provisioning file	Values (meaning)	Value type
Backup battery	BACKUP_BATTERY_PERCENT		Integer
Baseband firmware version	MODEM_FIRMWARE_VERSION		String
Battery Status	BATTERY_STATUS		String
Battery charging (Windows 8.1 Phone)	BATTERY_CHARGING	1 (True) 0 (False)	Boolean
Battery Charging (Windows 10)	BATTERY_CHARGING_STATUS	1 (True) 0 (False)	Boolean
Battery Remaining (Windows 10)	BATTERY_ESTIMATED_CHARGE_REMAINING		Integer
Bes device known by MSP	BES_DEVICE_KNOWN_BY_ZMSP	1 (True) 0 (False)	Boolean
BES PIN	BES_PIN		String
BES server agent ID	ENROLLMENT_AGENT_ID		String
BES server name	BES_SERVER		String
BES server version	BES_VERSION		String
BitLocker Status	WINDOWS_HAS_BIT_LOCKER_STATUS		String
Bluetooth MAC address	BLUETOOTH_MAC		String
Boot Debugging Enabled?	WINDOWS_HAS_BOOT_DEBUGGING_ENABLED		String

Property name in Manage > Devices page	Name and values for device provisioning file	Values (meaning)	Value type
Boot Manager Rev List Version	WINDOWS_HAS_BOOT_MGR_REV_LIST_VERSION		String
Carrier Code	CARRIER_CODE		String
Carrier settings version	CARRIER_SETTINGS_VERSION		String
Cellular latitude	GPS_LATITUDE_FROM_CELLULAR		String
Cellular longitude	GPS_LONGITUDE_FROM_CELLULAR		String
Cellular technology	CELLULAR_TECHNOLOGY		Integer
Cellular timestamp	GPS_TIMESTAMP_FROM_CELLULAR		Date
Change Password at Next Login?	GOOGLE_AW_DIRECTORY_CHANGE_PASSWORD_NEXT_LOGIN		String
Client device ID	CLIENT_DEVICE_ID		String
Cloud backup enabled	CLOUD_BACKUP_ENABLED	1 (Yes) 0 (No)	Boolean
Code Integrity Enabled?	WINDOWS_HAS_CODE_INTEGRITY_ENABLED		String
Code Integrity Rev List Version	WINDOWS_HAS_CODE_INTGTY_REV_LIST_VERSION		String
Color	COLOR		String
CPU clock speed	CPU_CLOCK_SPEED		Integer
CPU type	CPU_TYPE		String

Property name in Manage > Devices page	Name and values for device provisioning file	Values (meaning)	Value type
Creation Time	GOOGLE_AW_DIRECTORY_CREATION_TIME		String
Current carrier network	CURRENT_CARRIER_NETWORK		String
Current mobile country code	CURRENT_MCC		Integer
Current mobile network code	CURRENT_MNC		String
DEP account name	BULK_ENROLLMENT_DEP_ACCOUNT_NAME		String
DEP Policy	WINDOWS_HAS_DEP_POLICY		String
Data roaming allowed	DATA_ROAMING_ENABLED	1 (Yes) 0 (No)	Boolean
Date of the last iCloud backup	LAST_CLOUD_BACKUP_DATE		Date
Description	DESCRIPTION		String
Device Enrollment Program profile assigned	PROFILE_ASSIGN_TIME		Date
Device Enrollment Program profile pushed	PROFILE_PUSH_TIME		Date
Device Enrollment Program profile removed	PROFILE_REMOVE_TIME		Date
Device Enrollment Program registration by	DEVICE_ASSIGNED_BY		String

Property name in Manage > Devices page	Name and values for device provisioning file	Values (meaning)	Value type
Device Enrollment Program registration date	DEVICE_ASSIGNED_DATE		Date
Device Type	DEVICE_TYPE		String
Device model	MODEL_ID		String
Device name	DEVICE_NAME		String
Do Not Disturb activated	DO_NOT_DISTURB	1 (Yes) 0 (No)	Boolean
ELAM Driver Loaded?	WINDOWS_HAS_ELAM_DRIVER_LOADED		String
Encryption Compliance (Windows 10)	ENCRYPTION_COMPLIANCE	Encrypted Not Encrypted	String
ENROLLMENT_KEY_GENERATION_DATE	ENROLLMENT_KEY_GENERATION_DATE		Date
Enterprise ID	ENTERPRISE_ID		String
External storage 1: available space	EXTERNAL_STORAGE1_FREE_SPACE		Integer
External storage 1: name	EXTERNAL_STORAGE1_NAME		String
External storage 1: total space	EXTERNAL_STORAGE1_TOTAL_SPACE		Integer
External storage 2: available space	EXTERNAL_STORAGE2_FREE_SPACE		Integer
External storage 2: name	EXTERNAL_STORAGE2_NAME		String

Property name in Manage > Devices page	Name and values for device provisioning file	Values (meaning)	Value type
External storage 2: total space	EXTERNAL_STORAGE2_TOTAL_SPACE		Integer
External storage encrypted	EXTERNAL_ENCRYPTION	1 (Yes) 0 (No)	Boolean
Firewall Status (Windows 8.1 Phone)	FIREWALL_STATUS		String
Firewall Status (Windows 10)	DEVICE_FIREWALL_STATUS	On and monitoring Disabled Off or not monitoring Temporarily not monitoring N/A	String
Firmware version	FIRMWARE_VERSION		String
First synchronization	ZMSP_FIRST_SYNC		Date
GPS altitude	GPS_ALTITUDE_FROM_GPS		String
GPS latitude	GPS_LATITUDE_FROM_GPS		String
GPS longitude	GPS_LONGITUDE_FROM_GPS		String
GPS timestamp	GPS_TIMESTAMP_FROM_GPS		Date
Google Directory Alias	GOOGLE_AW_DIRECTORY_GOOGLE_ALIAS		String
Google Directory Family Name	GOOGLE_AW_DIRECTORY_FAMILY_NAME		String
Google Directory Name	GOOGLE_AW_DIRECTORY_NAME		String

Property name in Manage > Devices page	Name and values for device provisioning file	Values (meaning)	Value type
Google Directory Primary Email	GOOGLE_AW_DIRECTORY_PRIMARY		String
Google Directory User ID	GOOGLE_AW_DIRECTORY_USER_ID		String
HAS_CONTAINER	HAS_CONTAINER	1 (Yes) 0 (No)	Boolean
HTC API version	HTC_MDM_VERSION		String
HTC MDM API available	HTC_MDM	1 (Yes) 0 (No)	Boolean
Hardware encryption capabilities	HARDWARE_ENCRYPTION_CAPS		Integer
Hash of the iTunes store account currently logged on	ITUNES_STORE_ACCOUNT_HASH		String
Home carrier network	SIM_CARRIER_NETWORK		String
Home mobile country code	SIM_MCC		Integer
Home mobile network code	SIM_MNC		String
ICCID	ICCID		String
IMEI/MEID number	IMEI		String
IMSI	IMSI		String
IP location	IP_LOCATION		String

Property name in Manage > Devices page	Name and values for device provisioning file	Values (meaning)	Value type
Identity	AS_DEVICE_IDENTITY		String
Internal storage encrypted	LOCAL_ENCRYPTION	1 (True) 0 (False)	Boolean
IPV4 Address (Windows 10)	IP_ADDRESSV4		String
IPV6 Address (Windows 10)	IP_ADDRESSV6		String
Issued At	WINDOWS_HAS_ISSUED_AT		String
Jailbroken/Rooted	ROOT_ACCESS	1 (Yes) 0 (No)	Boolean
Kernel Debugging Enabled?	WINDOWS_HAS_OS_KERNEL_DEBUGGING_ENABLED		String
Kiosk mode	IS_KIOSK	1 (True) 0 (False)	Boolean
LSA Credential Guard Status	DEVICE_GUARD_LsaCfgCredGuardStatus	Running Reboot required Not licensed for Credential Guard Not configured VBS not running	String
Last known IP address	LAST_IP_ADDR		String
Last policy update time	LAST_POLICY_UPDATE_TIME		Date

Property name in Manage > Devices page	Name and values for device provisioning file	Values (meaning)	Value type
Last synchronization	ZMSP_LAST_SYNC	Number of days since last sync	Integer
Locator service enabled	DEVICE_LOCATOR	1 (Yes) 0 (No)	Boolean
MAC Address Network Connection (Windows 10)	MAC_NETWORK_CONNECTION	1 (Yes) 0 (No)	Boolean
MAC Address Type (Windows 10)	MAC_ADDRESS_TYPE	Unknown LAN WLAN	String
MDX_SHARED_ENCRYPTION_KEY	MDX_SHARED_ENCRYPTION_KEY		String
MEID	MEID		String
Mailbox Setup	GOOGLE_AW_DIRECTORY_MAILBOX_SETUP		String
Main battery	MAIN_BATTERY_PERCENT		Integer
Mobile phone number	TEL_NUMBER		String
Model ID	SYSTEM_OEM		String
Model Number	MODEL_NUMBER		String
Network Adapter Type	NETWORK_ADAPTER_TYPE		String
NitroDesk TouchDown installed	TOUCHDOWN_FIND	1 (True) 0 (False)	Boolean

Property name in Manage > Devices page	Name and values for device provisioning file	Values (meaning)	Value type
NitroDesk TouchDown licensed via MDM	TOUCHDOWN_LICENSED_VIA_MDM	1 (True) 0 (False)	Boolean
Operating system build	SYSTEM_OS_BUILD		String
Operating System Edition (Windows 10)	OS_EDITION		String
Operating system language (locale)	SYSTEM_LANGUAGE		String
Operating system version	SYSTEM_OS_VERSION		String
Organization address	ORGANIZATION_ADDRESS		String
Organization email	ORGANIZATION_EMAIL		String
Organization magic	ORGANIZATION_MAGIC		String
Organization name	ORGANIZATION_NAME		String
Organization phone number	ORGANIZATION_PHONE		String
Other	OTHER		String
Out of Compliance	OUT_OF_COMPLIANCE	1 (True) 0 (False)	Boolean
Owned by	CORPORATE_OWNED	1 (Corporate) 0 (BYOD)	Boolean
PCRO	WINDOWS_HAS_PCRO		String

Property name in Manage > Devices page	Name and values for device provisioning file	Values (meaning)	Value type
PIN code for geofence	PIN_CODE_FOR_GEO_FENCE		String
Passcode compliant	PASSCODE_IS_COMPLIANT	1 (Yes) 0 (No)	Boolean
Passcode compliant with configuration	PASSCODE_IS_COMPLIANT_WITH_CFG	1 (Yes) 0 (No)	Boolean
Passcode present	PASSCODE_PRESENT	1 (Yes) 0 (No)	Boolean
Perimeter breach	GPS_PERIMETER_BREACH	1 (Yes) 0 (No)	Boolean
Personal Hotspot activated	PERSONAL_HOTSPOT_ENABLED	1 (Yes) 0 (No)	Boolean
Platform	SYSTEM_PLATFORM		String
Platform API level	API_LEVEL		Integer
Policy name	POLICY_NAME		String
Primary Phone Number	IDENTITY1_PHONENUMBER		String
Primary SIM Carrier Operator (Windows 10)	IDENTITY1_CARRIER_NETWORK_OPERATOR		String
Primary SIM ICCID (Windows 10)	IDENTITY1_ICCID		String
Primary SIM IMEI	IDENTITY1_IMEI		String

Property name in Manage > Devices page	Name and values for device provisioning file	Values (meaning)	Value type
Primary SIM IMSI	IDENTITY1_IMSI		String
Primary SIM Roaming	IDENTITY1_ROAMING	1 (True) 0 (False)	Boolean
Primary SIM Roaming Compliance (Windows 10)	IDENTITY1_ROAMING_COMPLIANCE	1 (True) 0 (False)	Boolean
Product name	PRODUCT_NAME		String
Publisher Device ID	PUBLISHER_DEVICE_ID		String
Reset Count	WINDOWS_HAS_RESET_COUNT		String
Restart Count	WINDOWS_HAS_RESTART_COUNT		String
SBCP Hash	WINDOWS_HAS_SBCP_HASH		String
SMS capable	IS_SMS_CAPABLE	1 (True) 0 (False)	Boolean
Safe Mode Enabled?	WINDOWS_HAS_SAFE_MODE		String
Samsung KNOX API available	SAMSUNG_KNOX	1 (True) 0 (False)	Boolean
Samsung KNOX API version	SAMSUNG_KNOX_VERSION		String
Samsung KNOX attestation	SAMSUNG_KNOX_ATTESTED	1 (Passed) 0 (Failed)	Boolean

Property name in Manage > Devices page	Name and values for device provisioning file	Values (meaning)	Value type
Samsung KNOX attestation measurement details	SAMSUNG_KNOX_ATT_CONTENT		String
Samsung KNOX attestation updated date	SAMSUNG_KNOX_ATT_UPDATED_TIME		Date
Samsung SAFE API available	SAMSUNG_MDM	1 (True) 0 (False)	Boolean
Samsung SAFE API version	SAMSUNG_MDM_VERSION		String
Screen: X-axis resolution	SCREEN_XDPI		Integer (PPI)
Screen: Y-axis resolution	SCREEN_YDPI		Integer (PPI)
Screen: height	SCREEN_HEIGHT		Integer (pixels)
Screen: number of colors	SCREEN_NB_COLORS		Integer
Screen: size	SCREEN_SIZE		Decimal (inches)
Screen: width	SCREEN_WIDTH		Integer (pixels)
Secondary Phone Number	IDENTITY2_PHONENUMBER		String
Secondary SIM IMEI	IDENTITY2_IMEI		String
Secondary SIM IMSI	IDENTITY2_IMSI		String

Property name in Manage > Devices page	Name and values for device provisioning file	Values (meaning)	Value type
Secondary SIM Roaming	IDENTITY2_ROAMING	1 (True) 0 (False)	Boolean
Secure Boot Enabled? (Windows 8.1 Phone)	WINDOWS_HAS_SECURE_BOOT_ENABLED		String
Secure Boot Status (Windows 10)	SECURE_BOOT_STATE	Not supported Enabled Disabled	String
SecureContainer Enabled	WINDOWS_HAS_BIT_LOCKER_STATUS		String
Serial number	SERIAL_NUMBER		String
Slot one -- ICCID	ICCID_SLOT_ONE		String
Slot one -- phone number	PHONENUMBER_SLOT_ONE		String
Slot one -- IMEI	IMEI_SLOT_ONE		String
Slot one -- MEID	MEID_SLOT_ONE		String
Slot one -- eSIM status	IS_ESIM_SLOT_ONE	1 (True) 0 (False)	Boolean
Slot one -- home carrier network	SIM_CARRIER_NETWORK_SLOT_ONE		String
Slot one -- current mobile country code	CURRENT_MCC_SLOT_ONE		String
Slot one -- current mobile network code	CURRENT_MNC_SLOT_ONE		String
Slot one -- EID	EID_SLOT_ONE		String

Property name in Manage > Devices page	Name and values for device provisioning file	Values (meaning)	Value type
Slot two -- ICCID	ICCID_SLOT_TWO		String
Slot two -- phone number	PHONENUMBER_SLOT_TWO		String
Slot two -- IMEI	IMEI_SLOT_TWO		String
Slot two -- MEID	MEID_SLOT_TWO		String
Slot two -- eSIM status	IS_ESIM_SLOT_TWO	1 (True) 0 (False)	Boolean
Slot two -- home carrier network	SIM_CARRIER_NETWORK_SLOT_TWO		String
Slot two -- current mobile country code	CURRENT_MCC_SLOT_TWO		String
Slot two -- current mobile network code	CURRENT_MNC_SLOT_TWO		String
Slot two -- EID	EID_SLOT_TWO		String
Sony Enterprise API available	SONY_MDM	1 (True) 0 (False)	Boolean
Sony Enterprise API version	SONY_MDM_VERSION		String
Supervised	Supervised	1 (Yes) 0 (No)	Boolean
Suspension Reason	GOOGLE_AW_DIRECTORY_SUSPENSION_REASON		String
Tampered Status	TAMPERED_STATUS		String

Terms & Conditions	TERMS_AND_CONDITIONS	String
--------------------	----------------------	--------

Property name in Manage > Devices page	Name and values for device provisioning file	Values (meaning)	Value type
Terms And Agreement Accepted?	GOOGLE_AW_DIRECTORY_AGREED_TO_TERMS		String
Test Signing Enabled?	WINDOWS_HAS_TEST_SIGNING_ENABLED		String
Total RAM	MEMORY		Integer
Total storage space	FREEDISK		Integer
TPM Version (Windows 10)	TPM_VERSION		String
UDID	UDID		String
		Not supported Enabled Disabled	
User Account Control Status (Windows 10)	UAC_STATUS		String
User agent	USER_AGENT		String
User defined #1	USER_DEFINED_1		String
User defined #2	USER_DEFINED_2		String
User defined #3	USER_DEFINED_3		String
User language (locale)	USER_LANGUAGE		String
VSM Enabled?	WINDOWS_HAS_VSM_ENABLED		String

Vendor	VENDOR	String
--------	--------	--------

Property name in Manage > Devices page	Name and values for device provisioning file	Values (meaning)	Value type
Voice capable	IS_VOICE_CAPABLE	1 (True) 0 (False)	Boolean
Voice roaming allowed	VOICE_ROAMING_ENABLED	1 (Yes) 0 (No)	Boolean
VBS Hardware Requirement Status	DEVICE_GUARD_VBS_HW_REQ	System meets hardware configuration requirements SecureBoot required DMA Protection required HyperV not supported for Guest VM HyperV feature is not available	String
VBS Status	DEVICE_GUARD_VBS_STATUS	Running Reboot required 64 bit architecture required Not licensed Not configured System doesn't meet hardware requirements Other. Event logs in Microsoft-Windows-DeviceGuard have more details	String
WINDOWS_ENROLLMENT_KEY	WINDOWS_ENROLLMENT_KEY		String
WNS Notification Status	WNS_PUSH_STATUS		String
WNS Notification URL	PROPERTY_WNS_PUSH_URL		String
WNS Notification URL expiry date	PROPERTY_WNS_PUSH_URL_EXPIRY		String

WiFi MAC address	WIFI_MAC	String
------------------	----------	--------

Property name in Manage > Devices page	Name and values for device provisioning file	Values (meaning)	Value type
WinPE Enabled?	WINDOWS_HAS_WINPE		String
XenMobile agent ID	AGENT_ID		String
XenMobile agent revision	EW_REVISION		String
XenMobile agent version	EW_VERSION		String