

# Configuring ScreenSteps


Configuring ScreenSteps for single sign-on (SSO) enables administrators to manage users of Citrix ADC. Users can securely log on to ScreenSteps by using the enterprise credentials.

## Prerequisite


Browser Requirements: Internet Explorer 11 and above

## To configure ScreenSteps for SSO by using SAML:


1. In a browser, type <https://screenstepslive.com>, and press **Enter**.
2. To locate your admin account, type your **Account name** and click **Find Account**.



3. After locating the account, log on to the ScreenSteps account with your credentials (**Username** and **Password**).



- To create **Single Sign-On Endpoint**, click the **Account** menu that is present at the top-right corner of the screen, and select **Single Sign-On**.



- Click **Create Single Sign-on Endpoint**.
- To create **Single Sign-On Endpoint**, enter the values for the following fields as explained in the following table:

Field	Description
Title	Citrix ADC
Mode	Select <b>SAML</b> from the drop-down list.
Remote Login URL	IdP logon URL
Remote Logout URL	IdP logout URL

 A screenshot of the 'Create Single Sign-on Endpoint' form. The form has a title 'Create Single Sign-on Endpoint' in blue. It contains four input fields: 'Title' (text input), 'Mode' (dropdown menu with 'SAML' selected), 'Remote Login URL' (text input), and 'Log out URL' (text input). A blue 'Create' button is located at the bottom left of the form.

- After providing all the relevant details, click **Create**.  
**Note:** A confirmation message indicating that the SSO Endpoint is created appears.
- In the **Edit Single Sign-On Endpoint** section, click **SAML Certificate**, upload the certificate and click **Update**. To obtain the certificate, refer the following table:

Field name	Description
Certificate	Copy and paste the IdP certificate. The IdP certificate must begin and end with -----Begin Certificate----- and -----End Certificate----- <b>Note:</b> The IdP certificate is provided by Citrix and can be accessed from the link below: <a href="https://ssb4.mgmt.netScalerGatewaydev.net/idp/saml/templatetest/idp_metadata.xml">https://ssb4.mgmt.netScalerGatewaydev.net/idp/saml/templatetest/idp_metadata.xml</a>

9. After configuring the single sign-on Endpoint, copy both the SAML URLs, and test them in the testing site.

**URLs**

SAML Consumer URL

SAML Test URL