


Configuring Domo

Users can securely log on to Domo using their enterprise credentials. To configure Domo for single sign on through SAML, follow the steps below:

1. In a browser, type the URL in `https://<your-organization>.domo.com` format and press Enter.
2. Log on to your Domo account.

A screenshot of the Domo login interface. At the top center is the Domo logo, which consists of a blue square with the word "DOMO" in white, uppercase letters. Below the logo are two input fields: the first is labeled "Email" with an envelope icon, and the second is labeled "Password" with a key icon. Below these fields is a prominent orange button with the text "SIGN IN" in white. Underneath the button, there is a checkbox labeled "Remember me" and a link labeled "Forgot password?". At the bottom of the form, there is a line of text: "By signing in, you agree to the [Domo, Inc. Service Agreement](#) and [Patents](#)".

DOMO

Email


Password

SIGN IN


Remember me [Forgot password?](#)

By signing in, you agree to the [Domo, Inc. Service Agreement](#) and [Patents](#)

3. On the home page, in the upper right corner, click  > **Admin**.



4. On the **Admin Settings** page, click **Security** > **Single Sign-On (SSO)** > **Enable SSO**.



5. In the **Single Sign-On (SSO)** section, provide the following information.

Single Sign-On (SSO) REVERT ALL SAVE CONFIG TEST CONFIG

Configure Domo to work with your identity provider (IdP) to allow SSO from your company. You can also set it up using the [wizard](#). [BETA](#)

MANUAL SETUP DIRECT SIGN ON LIST ATTRIBUTES

Enable SSO

Information from your IdP

To fill out this form, you'll need to open your IdP and find the information in its SSO setup. Your IdP may also have a metadata file with all this data that you can upload here.

Metadata upload ?

- i. In the **MANUAL SETUP** section, under **Information from your IdP**, specify the IdP information.
Note: If you want to upload a metadata file, click **Metadata upload** or, to continue adding information manually click **Manual Entry**.
- ii. In the **Identity provider endpoint URL** box, type the URL in `https://<your-organization>/saml/login` format.

Identity provider endpoint URL ?

https://[redacted]/saml/login

- iii. In the **Entity ID** box, type a unique(org url) entity ID.

Entity ID ?

https://[redacted]

- iv. In the **Upload x.509 certificate to authenticate request** box, upload the IdP certificate.

Upload x.509 certificate to authenticate request ?

Certificate Uploaded

View certificate

Click the arrow to browse to the folder where you saved the IdP provided certificate and upload it.

- vi. In the **Advanced settings** area, select the **On logout, direct people to the following URL** check box and type a redirect URL for logging out.

Advanced settings ?

- Only invited people can access Domo
- On logout, direct people to the following URL:
- Use SAML Relay State to redirect
- Import groups from identity provider
- Show Domo sign-in screen Skip to identity provider
- Mixed mode login

6. In the upper-right corner, click **SAVE CONFIG**.
7. To test the configuration, click **TEST CONFIG**.

Single Sign-On (SSO)

Configure Domo to work with your identity provider (IdP) to allow SSO from your company. You can also set it up using the [wizard](#). BETA

REVERT ALL SAVE CONFIG TEST CONFIG

You have completed the required configuration on the service provider which is in this case – Domo.