

# Configure Resource Guru for Single Sign-On


Configuring Resource Guru for single sign-on (SSO) enables administrators to manage users of Citrix ADC. Users can securely log on to Resource Guru by using the enterprise credentials.

## Prerequisite

Browser Requirements: Internet Explorer 11 and above

## To configure Resource Guru for SSO by using SAML:

1. In a browser, type <https://resourceguruapp.com/login> and press **Enter**.
2. Type your Resource Guru admin account credentials (**Email** and **Password**) and click **Log in**.



Log in with your Resource Guru ID


.....

Remember me on this computer


Log in

[Forgotten your password?](#)


3. In the dashboard page, click the user account icon in the top-right corner and select **Settings**.



4. In the **SETTINGS** page, click **SSO** in the left pane.



5. In the **SSO/SAML (Single Sign On) Configuration** page, click **Configure SSO**.



6. Enter the values for the following fields:

Required Information	Description
Email domain*	Email domain

SSO URL/Endpoint*	IdP logon URL
IdP Entity ID*	Issuer URL
IdP X.509 Certificate	<p>Copy and paste the IdP certificate. The IdP certificate must begin and end with  -----Begin Certificate----- and -----End Certificate-----</p> <p><b>Note:</b> The IdP metadata is provided by Citrix and can be accessed from the link below. The link is displayed while configuring SSO settings for your app.  <a href="https://gateway.cloud.com/idp/saml/&lt;citrixcloudcust_id&gt;/&lt;app_id&gt;/idp_metadata.xml">https://gateway.cloud.com/idp/saml/&lt;citrixcloudcust_id&gt;/&lt;app_id&gt;/idp_metadata.xml</a></p>

## New SSO Configuration ✕

SSO needs to be configured in both your Resource Guru account and your Identity Provider (IdP) account. You will need the following when setting up SSO with your IdP:

- ACS URL: <https://resourceguruapp.com/sso/acs>
- Entity ID: resource-guru

Email domain \*

SSO URL/Endpoint \*

IdP Entity ID \*

IdP X.509 Certificate \*  samlcert.pem

Users must be invited  Self-service

Users can login with SSO or password  SSO only

7. Finally, click **Add Configuration**.